

SystemTap Tapset Reference Manual

SystemTap

SystemTap Tapset Reference Manual

by SystemTap

Copyright © 2008-2013 Red Hat, Inc. and others

This documentation is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License version 2 as published by the Free Software Foundation.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA.

For more details see the file COPYING in the source distribution of Linux.

Table of Contents

1. Introduction	1
2. Context Functions	2
function::addr	3
function::asmlinkage	4
function::backtrace	5
function::caller	6
function::caller_addr	7
function::callers	8
function::cmdline_arg	9
function::cmdline_args	10
function::cmdline_str	11
function::cpu	12
function::cpuid	13
function::egid	14
function::env_var	15
function::euid	16
function::execname	17
function::fastcall	18
function::gid	19
function::int_arg	20
function::is_myproc	21
function::is_return	22
function::long_arg	23
function::longlong_arg	24
function::modname	25
function::module_name	26
function::pexecname	27
function::pgrp	28
function::pid	29
function::pid2execname	30
function::pid2task	31
function::pn	32
function::pointer_arg	33
function::pp	34
function::ppfunc	35
function::ppid	36
function::print_backtrace	37
function::print_regs	38
function::print_stack	39
function::print_syms	40
function::print_ubacktrace	41
function::print_ubacktrace_brief	42
function::print_ustack	43
function::print_usyms	44
function::probe_type	45
function::probefunc	46
function::probemod	47
function::pstrace	48
function::register	49
function::registers_valid	50
function::regparm	51
function::remote_id	52
function::remote_uri	53
function::s32_arg	54
function::s64_arg	55

function::sid	56
function::sprint_backtrace	57
function::sprint_stack	58
function::sprint_syms	59
function::sprint_ubacktrace	60
function::sprint_ustack	61
function::sprint_usyms	62
function::stack	63
function::stack_size	64
function::stack_unused	65
function::stack_used	66
function::stp_pid	67
function::syndata	68
function::symname	69
function::target	70
function::task_backtrace	71
function::task_cpu	72
function::task_current	73
function::task_egid	74
function::task_euid	75
function::task_execname	76
function::task_gid	77
function::task_max_file_handles	78
function::task_nice	79
function::task_open_file_handles	80
function::task_parent	81
function::task_pid	82
function::task_prio	83
function::task_state	84
function::task_tid	85
function::task_uid	86
function::tid	87
function::u32_arg	88
function::u64_arg	89
function::u_register	90
function::uaddr	91
function::ubacktrace	92
function::ucallers	93
function::uid	94
function::uint_arg	95
function::ulong_arg	96
function::ulonglong_arg	97
function::umodname	98
function::user_mode	99
function::ustack	100
function::usyndata	101
function::usymname	102
3. Timestamp Functions	103
function::HZ	104
function::cpu_clock_ms	105
function::cpu_clock_ns	106
function::cpu_clock_s	107
function::cpu_clock_us	108
function::delete_stopwatch	109
function::get_cycles	110
function::gettimeofday_ms	111
function::gettimeofday_ns	112
function::gettimeofday_s	113

function::gettimeofday_us	114
function::jiffies	115
function::local_clock_ms	116
function::local_clock_ns	117
function::local_clock_s	118
function::local_clock_us	119
function::read_stopwatch_ms	120
function::read_stopwatch_ns	121
function::read_stopwatch_s	122
function::read_stopwatch_us	123
function::start_stopwatch	124
function::stop_stopwatch	125
4. Time utility functions	126
function::ctime	127
function::tz_ctime	128
function::tz_gmtoff	129
function::tz_name	130
5. Shell command functions	131
function::system	132
6. Memory Tapset	133
function::addr_to_node	134
function::bytes_to_string	135
function::mem_page_size	136
function::pages_to_string	137
function::proc_mem_data	138
function::proc_mem_data_pid	139
function::proc_mem_rss	140
function::proc_mem_rss_pid	141
function::proc_mem_shr	142
function::proc_mem_shr_pid	143
function::proc_mem_size	144
function::proc_mem_size_pid	145
function::proc_mem_string	146
function::proc_mem_string_pid	147
function::proc_mem_txt	148
function::proc_mem_txt_pid	149
function::vm_fault_contains	150
probe::vm.brk	151
probe::vm.kfree	152
probe::vm.kmalloc	153
probe::vm.kmalloc_node	154
probe::vm.kmem_cache_alloc	155
probe::vm.kmem_cache_alloc_node	156
probe::vm.kmem_cache_free	157
probe::vm.mmap	158
probe::vm.munmap	159
probe::vm.oom_kill	160
probe::vm.pagefault	161
probe::vm.pagefault.return	162
probe::vm.write_shared	163
probe::vm.write_shared_copy	164
7. Task Time Tapset	165
function::cputime_to_msecs	166
function::cputime_to_string	167
function::cputime_to_usecs	168
function::msecs_to_string	169
function::task_stime	170
function::task_stime_tid	171

function::task_time_string	172
function::task_time_string_tid	173
function::task_utime	174
function::task_utime_tid	175
function::usecs_to_string	176
8. Scheduler Tapset	177
probe::scheduler.balance	178
probe::scheduler.cpu_off	179
probe::scheduler.cpu_on	180
probe::scheduler.ctxswitch	181
probe::scheduler.kthread_stop	182
probe::scheduler.kthread_stop.return	183
probe::scheduler.migrate	184
probe::scheduler.process_exit	185
probe::scheduler.process_fork	186
probe::scheduler.process_free	187
probe::scheduler.process_wait	188
probe::scheduler.signal_send	189
probe::scheduler.tick	190
probe::scheduler.wait_task	191
probe::scheduler.wakeup	192
probe::scheduler.wakeup_new	193
9. IO Scheduler and block IO Tapset	194
probe::ioblock.end	195
probe::ioblock.request	196
probe::ioblock_trace.bounce	197
probe::ioblock_trace.end	198
probe::ioblock_trace.request	199
probe::ioscheduler.elv_add_request	200
probe::ioscheduler.elv_add_request.kp	201
probe::ioscheduler.elv_add_request.tp	202
probe::ioscheduler.elv_completed_request	203
probe::ioscheduler.elv_next_request	204
probe::ioscheduler.elv_next_request.return	205
probe::ioscheduler_trace.elv_abort_request	206
probe::ioscheduler_trace.elv_completed_request	207
probe::ioscheduler_trace.elv_issue_request	208
probe::ioscheduler_trace.elv_requeue_request	209
probe::ioscheduler_trace.plug	210
probe::ioscheduler_trace.unplug_io	211
probe::ioscheduler_trace.unplug_timer	212
10. SCSI Tapset	213
probe::scsi.iocompleted	214
probe::scsi.iodispatching	215
probe::scsi.iodone	216
probe::scsi.ioentry	217
probe::scsi.ioexecute	218
probe::scsi.set_state	219
11. TTY Tapset	220
probe::tty.init	221
probe::tty.ioctl	222
probe::tty.open	223
probe::tty.poll	224
probe::tty.read	225
probe::tty.receive	226
probe::tty.register	227
probe::tty.release	228
probe::tty.resize	229

probe::tty.unregister	230
probe::tty.write	231
12. Interrupt Request (IRQ) Tapset	232
probe::irq_handler.entry	233
probe::irq_handler.exit	234
probe::softirq.entry	235
probe::softirq.exit	236
probe::workqueue.create	237
probe::workqueue.destroy	238
probe::workqueue.execute	239
probe::workqueue.insert	240
13. Networking Tapset	241
function::format_ipaddr	242
function::htonl	243
function::htonll	244
function::htons	245
function::ip_ntop	246
function::ntohl	247
function::ntohll	248
function:: ntohs	249
probe::netdev.change_mac	250
probe::netdev.change_mtu	251
probe::netdev.change_rx_flag	252
probe::netdev.close	253
probe::netdev.get_stats	254
probe::netdev.hard_transmit	255
probe::netdev.ioctl	256
probe::netdev.open	257
probe::netdev.receive	258
probe::netdev.register	259
probe::netdev.rx	260
probe::netdev.set_promiscuity	261
probe::netdev.transmit	262
probe::netdev.unregister	263
probe::netfilter.arp.forward	264
probe::netfilter.arp.in	265
probe::netfilter.arp.out	266
probe::netfilter.bridge.forward	267
probe::netfilter.bridge.local_in	268
probe::netfilter.bridge.local_out	269
probe::netfilter.bridge.post_routing	270
probe::netfilter.bridge.pre_routing	271
probe::netfilter.ip.forward	272
probe::netfilter.ip.local_in	274
probe::netfilter.ip.local_out	276
probe::netfilter.ip.post_routing	278
probe::netfilter.ip.pre_routing	280
probe::sunrpc.clntr.bind_new_program	282
probe::sunrpc.clntr.call_async	283
probe::sunrpc.clntr.call_sync	284
probe::sunrpc.clntr.clone_client	285
probe::sunrpc.clntr.create_client	286
probe::sunrpc.clntr.restart_call	287
probe::sunrpc.clntr.shutdown_client	288
probe::sunrpc.sched.delay	289
probe::sunrpc.sched.execute	290
probe::sunrpc.sched.new_task	291
probe::sunrpc.sched.release_task	292

probe::sunrpc.svc.create	293
probe::sunrpc.svc.destroy	294
probe::sunrpc.svc.drop	295
probe::sunrpc.svc.process	296
probe::sunrpc.svc.recv	297
probe::sunrpc.svc.register	298
probe::sunrpc.svc.send	299
probe::tcp.disconnect	300
probe::tcp.disconnect.return	301
probe::tcp.receive	302
probe::tcp.recvmsg	303
probe::tcp.recvmsg.return	304
probe::tcp.sendmsg	305
probe::tcp.sendmsg.return	306
probe::tcp.setsockopt	307
probe::tcp.setsockopt.return	308
probe::udp.disconnect	309
probe::udp.disconnect.return	310
probe::udp.recvmsg	311
probe::udp.recvmsg.return	312
probe::udp.sendmsg	313
probe::udp.sendmsg.return	314
14. Socket Tapset	315
function::inet_get_ip_source	316
function::inet_get_local_port	317
function::sock_fam_num2str	318
function::sock_fam_str2num	319
function::sock_prot_num2str	320
function::sock_prot_str2num	321
function::sock_state_num2str	322
function::sock_state_str2num	323
probe::socket.aio_read	324
probe::socket.aio_read.return	325
probe::socket.aio_write	326
probe::socket.aio_write.return	327
probe::socket.close	328
probe::socket.close.return	329
probe::socket.create	330
probe::socket.create.return	331
probe::socket.readv	332
probe::socket.ready.return	333
probe::socket.receive	334
probe::socket.recvmsg	335
probe::socket.recvmsg.return	336
probe::socket.send	337
probe::socket.sendmsg	338
probe::socket.sendmsg.return	339
probe::socket.writev	340
probe::socket.writev.return	341
15. SNMP Information Tapset	342
function::ipmib_filter_key	343
function::ipmib_get_proto	344
function::ipmib_local_addr	345
function::ipmib_remote_addr	346
function::ipmib_tcp_local_port	347
function::ipmib_tcp_remote_port	348
function::linuxmib_filter_key	349
function::tcpmib_filter_key	350

function::tcpmib_get_state	351
function::tcpmib_local_addr	352
function::tcpmib_local_port	353
function::tcpmib_remote_addr	354
function::tcpmib_remote_port	355
probe::ipmib.ForwDatagrams	356
probe::ipmib.FragFails	357
probe::ipmib.FragOKs	358
probe::ipmib.InAddrErrors	359
probe::ipmib.InDiscards	360
probe::ipmib.InNoRoutes	361
probe::ipmib.InReceives	362
probe::ipmib.InUnknownProtos	363
probe::ipmib.OutRequests	364
probe::ipmib.ReasmReqds	365
probe::ipmib.ReasmTimeout	366
probe::linuxmib.DelayedACKs	367
probe::linuxmib.ListenDrops	368
probe::linuxmib.ListenOverflows	369
probe::linuxmib.TCPMemoryPressures	370
probe::tcpmib.ActiveOpens	371
probe::tcpmib.AttemptFails	372
probe::tcpmib.CurrEstab	373
probe::tcpmib.EstabResets	374
probe::tcpmib.InSegs	375
probe::tcpmib.OutRsts	376
probe::tcpmib.OutSegs	377
probe::tcpmib.PassiveOpens	378
probe::tcpmib.RetransSegs	379
16. Kernel Process Tapset	380
function::target_set_pid	381
function::target_set_report	382
probe::kprocess.create	383
probe::kprocess.exec	384
probe::kprocess.exec_complete	385
probe::kprocess.exit	386
probe::kprocess.release	387
probe::kprocess.start	388
17. Signal Tapset	389
function::get_sa_flags	390
function::get_sa_handler	391
function::is_sig_blocked	392
function::sa_flags_str	393
function::sa_handler_str	394
function::signal_str	395
function::sigset_mask_str	396
probe::signal.check_ignored	397
probe::signal.check_ignored.return	398
probe::signal.checkperm	399
probe::signal.checkperm.return	400
probe::signal.do_action	401
probe::signal.do_action.return	402
probe::signal.flush	403
probe::signal.force_segv	404
probe::signal.force_segv.return	405
probe::signal.handle	406
probe::signal.handle.return	407
probe::signal.pending	408

probe::signal.pending.return	409
probe::signal.procmask	410
probe::signal.procmask.return	411
probe::signal.send	412
probe::signal.send.return	413
probe::signal.send_sig_queue	414
probe::signal.send_sig_queue.return	415
probe::signal.sys_tkill	416
probe::signal.sys_tkill.return	417
probe::signal.sys_tkill	418
probe::signal.syskill	419
probe::signal.syskill.return	420
probe::signal.systkill.return	421
probe::signal.wakeup	422
18. Errno Tapset	423
function::errno_str	424
function::return_str	425
function::returnstr	426
function::returnval	427
19. Device Tapset	428
function::MAJOR	429
function::MINOR	430
function::MKDEV	431
function::usrdev2kerndev	432
20. Directory-entry (dentry) Tapset	433
function::d_name	434
function::d_path	435
function::inode_name	436
function::real_mount	437
function::reverse_path_walk	438
function::task_dentry_path	439
21. Logging Tapset	440
function::error	441
function::exit	442
function::ftrace	443
function::log	444
function::printk	445
function::warn	446
22. Queue Statistics Tapset	447
function::qs_done	448
function::qs_run	449
function::qs_wait	450
function::qsq_blocked	451
function::qsq_print	452
function::qsq_service_time	453
function::qsq_start	454
function::qsq_throughput	455
function::qsq_utilization	456
function::qsq_wait_queue_length	457
function::qsq_wait_time	458
23. Random functions Tapset	459
function::randint	460
24. String and data retrieving functions Tapset	461
function::atomic_long_read	462
function::atomic_read	463
function::kernel_char	464
function::kernel_int	465
function::kernel_long	466

function::kernel_pointer	467
function::kernel_short	468
function::kernel_string	469
function::kernel_string2	470
function::kernel_string2_utf16	471
function::kernel_string2_utf32	472
function::kernel_string_n	473
function::kernel_string_utf16	474
function::kernel_string_utf32	475
function::user_char	476
function::user_char_warn	477
function::user_int	478
function::user_int16	479
function::user_int32	480
function::user_int64	481
function::user_int8	482
function::user_int_warn	483
function::user_long	484
function::user_long_warn	485
function::user_short	486
function::user_short_warn	487
function::user_string	488
function::user_string2	489
function::user_string2_n_warn	490
function::user_string2_utf16	491
function::user_string2_utf32	492
function::user_string2_warn	493
function::user_string_n	494
function::user_string_n2	495
function::user_string_n_quoted	496
function::user_string_n_warn	497
function::user_string_quoted	498
function::user_string_utf16	499
function::user_string_utf32	500
function::user_string_warn	501
function::user_uint16	502
function::user_uint32	503
function::user_uint64	504
function::user_uint8	505
function::user_ushort	506
function::user_ushort_warn	507
25. String and data writing functions Tapset	508
function::set_kernel_char	509
function::set_kernel_int	510
function::set_kernel_long	511
function::set_kernel_pointer	512
function::set_kernel_short	513
function::set_kernel_string	514
function::set_kernel_string_n	515
26. Guru tapsets	516
function::mdelay	517
function::panic	518
function::raise	519
function::udelay	520
27. A collection of standard string functions	521
function::isdigit	522
function::isinstr	523
function::str_replace	524

function::stringat	525
function::strlen	526
function::strtol	527
function::substr	528
function::text_str	529
function::text_strn	530
function::tokenize	531
28. Utility functions for using ansi control chars in logs	532
function::ansi_clear_screen	533
function::ansi_cursor_hide	534
function::ansi_cursor_move	535
function::ansi_cursor_restore	536
function::ansi_cursor_save	537
function::ansi_cursor_show	538
function::ansi_new_line	539
function::ansi_reset_color	540
function::ansi_set_color	541
function::ansi_set_color2	542
function::ansi_set_color3	543
function::indent	544
function::thread_indent	545
29. SystemTap Translator Tapset	546
probe::stap.cache_add_mod	547
probe::stap.cache_add_nss	548
probe::stap.cache_add_src	549
probe::stap.cache_clean	550
probe::stap.cache_get	551
probe::stap.pass0	552
probe::stap.pass0.end	553
probe::stap.pass1.end	554
probe::stap.pass1a	555
probe::stap.pass1b	556
probe::stap.pass2	557
probe::stap.pass2.end	558
probe::stap.pass3	559
probe::stap.pass3.end	560
probe::stap.pass4	561
probe::stap.pass4.end	562
probe::stap.pass5	563
probe::stap.pass5.end	564
probe::stap.pass6	565
probe::stap.pass6.end	566
probe::stap.system	567
probe::stap.system.return	568
probe::stap.system.spawn	569
probe::stadio.receive_control_message	570
probe::staprun.insert_module	571
probe::staprun.remove_module	572
probe::staprun.send_control_message	573
30. Network File Storage Tapsets	574
function::nfserror	575
probe::nfs.aop.readpage	576
probe::nfs.aop.readpages	577
probe::nfs.aop.release_page	578
probe::nfs.aop.set_page_dirty	579
probe::nfs.aop.write_begin	580
probe::nfs.aop.write_end	581
probe::nfs.aop.writepage	582

probe::nfs.aop.writepages	583
probe::nfs.fop aio_read	584
probe::nfs.fop aio_write	585
probe::nfs.fop check_flags	586
probe::nfs.fop flush	587
probe::nfs.fop fsync	588
probe::nfs.fop llseek	589
probe::nfs.fop lock	590
probe::nfs.fop mmap	591
probe::nfs.fop open	592
probe::nfs.fop read	593
probe::nfs.fop release	594
probe::nfs.fop sendfile	595
probe::nfs.fop write	596
probe::nfs.proc.commit	597
probe::nfs.proc.commit_done	598
probe::nfs.proc.commit_setup	599
probe::nfs.proc.create	600
probe::nfs.proc.handle_exception	601
probe::nfs.proc.lookup	602
probe::nfs.proc.open	603
probe::nfs.proc.read	604
probe::nfs.proc.read_done	605
probe::nfs.proc.read_setup	606
probe::nfs.proc.release	607
probe::nfs.proc.remove	608
probe::nfs.proc.rename	609
probe::nfs.proc.write	610
probe::nfs.proc.write_done	611
probe::nfs.proc.write_setup	612
probe::nfsd.close	613
probe::nfsd.commit	614
probe::nfsd.create	615
probe::nfsd.createv3	616
probe::nfsd.dispatch	617
probe::nfsd.lookup	618
probe::nfsd.open	619
probe::nfsd.proc.commit	620
probe::nfsd.proc.create	621
probe::nfsd.proc.lookup	622
probe::nfsd.proc.read	623
probe::nfsd.proc.remove	624
probe::nfsd.proc.rename	625
probe::nfsd.proc.write	626
probe::nfsd.read	627
probe::nfsd.rename	628
probe::nfsd.unlink	629
probe::nfsd.write	630
31. Speculation	631
function::commit	632
function::discard	633
function::speculate	634
function::speculation	635

Chapter 1. Introduction

SystemTap provides free software (GPL) infrastructure to simplify the gathering of information about the running Linux system. This assists diagnosis of a performance or functional problem. SystemTap eliminates the need for the developer to go through the tedious and disruptive instrument, recompile, install, and reboot sequence that may be otherwise required to collect data.

SystemTap provides a simple command line interface and scripting language for writing instrumentation for a live running kernel. The instrumentation makes extensive use of the probe points and functions provided in the *tapset* library. This document describes the various probe points and functions.

Chapter 2. Context Functions

The context functions provide additional information about where an event occurred. These functions can provide information such as a backtrace to where the event occurred and the current register values for the processor.

function::addr

function::addr — Address of the current probe point.

Synopsis

```
addr:long()
```

Arguments

None

Description

Returns the instruction pointer from the current probe's register state. Not all probe types have registers though, in which case zero is returned. The returned address is suitable for use with functions like `symname` and `symdata`.

function::asmlinkage

function::asmlinkage — Mark function as declared asmlinkage

Synopsis

```
asmlinkage()
```

Arguments

None

Description

Call this function before accessing arguments using the *_arg functions if the probed kernel function was declared asmlinkage in the source.

function::backtrace

function::backtrace — Hex backtrace of current kernel stack

Synopsis

```
backtrace:string()
```

Arguments

None

Description

This function returns a string of hex addresses that are a backtrace of the kernel stack. Output may be truncated as per maximum string length (MAXSTRINGLEN). See `ubacktrace` for user-space backtrace.

function::caller

function::caller — Return name and address of calling function

Synopsis

```
caller:string()
```

Arguments

None

Description

This function returns the address and name of the calling function. This is equivalent to calling:
sprintf("s 0xx", symname(caller_addr), caller_addr)

function::caller_addr

function::caller_addr — Return caller address

Synopsis

```
caller_addr:long()
```

Arguments

None

Description

This function returns the address of the calling function.

function::callers

function::callers — Return first n elements of kernel stack backtrace

Synopsis

```
callers:string(n:long)
```

Arguments

n number of levels to descend in the stack (not counting the top level). If *n* is -1, print the entire stack.

Description

This function returns a string of the first *n* hex addresses from the backtrace of the kernel stack. Output may be truncated as per maximum string length (MAXSTRINGLEN).

function::cmdline_arg

function::cmdline_arg — Fetch a command line argument

Synopsis

```
cmdline_arg:string(n:long)
```

Arguments

n Argument to get (zero is the command itself)

Description

Returns argument the requested argument from the current process or the empty string when there are not that many arguments or there is a problem retrieving the argument. Argument zero is traditionally the command itself.

function::cmdline_args

function::cmdline_args — Fetch command line arguments from current process

Synopsis

```
cmdline_args:string(n:long,m:long,delim:string)
```

Arguments

- n* First argument to get (zero is the command itself)
- m* Last argument to get (or minus one for all arguments after n)
- delim* String to use to delimit arguments when more than one.

Description

Returns arguments from the current process starting with argument number n, up to argument m. If there are less than n arguments, or the arguments cannot be retrieved from the current process, the empty string is returned. If m is smaller than n then all arguments starting from argument n are returned. Argument zero is traditionally the command itself.

function::cmdline_str

function::cmdline_str — Fetch all command line arguments from current process

Synopsis

```
cmdline_str:string()
```

Arguments

None

Description

Returns all arguments from the current process delimited by spaces. Returns the empty string when the arguments cannot be retrieved.

function::cpu

function::cpu — Returns the current cpu number

Synopsis

```
cpu:long()
```

Arguments

None

Description

This function returns the current cpu number.

function::cpuid

function::cpuid — Returns the current cpu number

Synopsis

```
cpuid:long()
```

Arguments

None

Description

This function returns the current cpu number. Deprecated in SystemTap 1.4 and removed in SystemTap 1.5.

function::egid

function::egid — Returns the effective gid of a target process

Synopsis

```
egid:long()
```

Arguments

None

Description

This function returns the effective gid of a target process

function::env_var

function::env_var — Fetch environment variable from current process

Synopsis

```
env_var:string(name:string)
```

Arguments

name Name of the environment variable to fetch

Description

Returns the contents of the specified environment value for the current process. If the variable isn't set an empty string is returned.

function::euid

function::euid — Return the effective uid of a target process

Synopsis

```
euid:long()
```

Arguments

None

Description

Returns the effective user ID of the target process.

function::execname

function::execname — Returns the execname of a target process (or group of processes)

Synopsis

```
execname:string()
```

Arguments

None

Description

Returns the execname of a target process (or group of processes).

function::fastcall

function::fastcall — Mark function as declared fastcall

Synopsis

```
fastcall()
```

Arguments

None

Description

Call this function before accessing arguments using the *_arg functions if the probed kernel function was declared fastcall in the source.

function::gid

function::gid — Returns the group ID of a target process

Synopsis

```
gid:long()
```

Arguments

None

Description

This function returns the group ID of a target process.

function::int_arg

function::int_arg — Return function argument as signed int

Synopsis

```
int_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the value of argument *n* as a signed int (i.e., a 32-bit integer sign-extended to 64 bits).

function::is_myproc

function::is_myproc — Determines if the current probe point has occurred in the user's own process

Synopsis

```
is_myproc:long()
```

Arguments

None

Description

This function returns 1 if the current probe point has occurred in the user's own process.

function::is_return

function::is_return — Whether the current probe context is a return probe

Synopsis

```
is_return:long()
```

Arguments

None

Description

Returns 1 if the current probe context is a return probe, returns 0 otherwise.

function::long_arg

function::long_arg — Return function argument as signed long

Synopsis

```
long_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the value of argument *n* as a signed long. On architectures where a long is 32 bits, the value is sign-extended to 64 bits.

function::longlong_arg

function::longlong_arg — Return function argument as 64-bit value

Synopsis

```
longlong_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the value of argument *n* as a 64-bit value.

function::modname

function::modname — Return the kernel module name loaded at the address

Synopsis

```
modname:string(addr:long)
```

Arguments

addr The address to map to a kernel module name

Description

Returns the module name associated with the given address if known. If not known it will raise an error. If the address was not in a kernel module, but in the kernel itself, then the string “kernel” will be returned.

function::module_name

function::module_name — The module name of the current script

Synopsis

```
module_name:string( )
```

Arguments

None

Description

This function returns the name of the stab module. Either generated randomly (stab_[0-9a-f]+_[0-9a-f]+) or set by stab -m <module_name>.

function::pexecname

function::pexecname — Returns the execname of a target process's parent process

Synopsis

```
pexecname:string()
```

Arguments

None

Description

This function returns the execname of a target process's parent process.

function::pgrp

function::pgrp — Returns the process group ID of the current process

Synopsis

```
pgrp:long()
```

Arguments

None

Description

This function returns the process group ID of the current process.

function::pid

function::pid — Returns the ID of a target process

Synopsis

```
pid:long()
```

Arguments

None

Description

This function returns the ID of a target process.

function::pid2execname

function::pid2execname — The name of the given process identifier

Synopsis

```
pid2execname:string(pid:long)
```

Arguments

pid process identifier

Description

Return the name of the given process id.

function::pid2task

function::pid2task — The task_struct of the given process identifier

Synopsis

```
pid2task:long(pid:long)
```

Arguments

pid process identifier

Description

Return the task struct of the given process id.

function::pn

function::pn — Returns the active probe name

Synopsis

```
pn:string()
```

Arguments

None

Description

This function returns the script-level probe point associated with a currently running probe handler, including wild-card expansion effects. Context: The current probe point.

function::pointer_arg

function::pointer_arg — Return function argument as pointer value

Synopsis

```
pointer_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the unsigned value of argument *n*, same as ulong_arg. Can be used with any type of pointer.

function::pp

function::pp — Returns the active probe point

Synopsis

```
pp:string()
```

Arguments

None

Description

This function returns the fully-resolved probe point associated with a currently running probe handler, including alias and wild-card expansion effects. Context: The current probe point.

function::ppfunc

function::ppfunc — Returns the function name parsed from pp

Synopsis

```
ppfunc:string()
```

Arguments

None

Description

This returns the function name from the current pp. Not all pp have functions in them, in which case "" is returned.

function::ppid

function::ppid — Returns the process ID of a target process's parent process

Synopsis

```
ppid:long()
```

Arguments

None

Description

This function return the process ID of the target proccess's parent process.

function::print_backtrace

function::print_backtrace — Print kernel stack back trace

Synopsis

```
print_backtrace()
```

Arguments

None

Description

This function is equivalent to print_stack(backtrace), except that deeper stack nesting may be supported. See print_ubacktrace for user-space backtrace. The function does not return a value.

function::print_regs

function::print_regs — Print a register dump

Synopsis

```
print_regs()
```

Arguments

None

Description

This function prints a register dump. Does nothing if no registers are available for the probe point.

function::print_stack

function::print_stack — Print out kernel stack from string

Synopsis

```
print_stack(stk:string)
```

Arguments

stk String with list of hexadecimal addresses

Description

This function performs a symbolic lookup of the addresses in the given string, which is assumed to be the result of a prior call to backtrace.

Print one line per address, including the address, the name of the function containing the address, and an estimate of its position within that function. Return nothing.

NOTE

it is recommended to use `print_syms` instead of this function.

function::print_syms

function::print_syms — Print out kernel stack from string

Synopsis

```
print_syms(callers:string)
```

Arguments

callers String with list of hexadecimal (kernel) addresses

Description

This function performs a symbolic lookup of the addresses in the given string, which are assumed to be the result of prior calls to `stack`, `callers`, and similar functions.

Prints one line per address, including the address, the name of the function containing the address, and an estimate of its position within that function, as obtained by `symsdata`. Returns nothing.

function::print_ubacktrace

function::print_ubacktrace — Print stack back trace for current user-space task.

Synopsis

```
print_ubacktrace()
```

Arguments

None

Description

Equivalent to print_ustack(ubacktrace), except that deeper stack nesting may be supported. Returns nothing. See `print_backtrace` for kernel backtrace.

Note

To get (full) backtraces for user space applications and shared shared libraries not mentioned in the current script run `stap` with `-d /path/to/exe-or-so` and/or add `--ldd` to load all needed unwind data.

function::print_ubacktrace_brief

function::print_ubacktrace_brief — Print stack back trace for current user-space task.

Synopsis

```
print_ubacktrace_brief()
```

Arguments

None

Description

Equivalent to `print_ubacktrace`, but output for each symbol is shorter (just name and offset, or just the hex address of no symbol could be found).

Note

To get (full) backtraces for user space applications and shared shared libraries not mentioned in the current script run `stap` with `-d /path/to/exe-or-so` and/or add `--ldd` to load all needed unwind data.

function::print_ustack

function::print_ustack — Print out stack for the current task from string.

Synopsis

```
print_ustack(stk:string)
```

Arguments

stk String with list of hexadecimal addresses for the current task.

Description

Perform a symbolic lookup of the addresses in the given string, which is assumed to be the result of a prior call to `ubacktrace` for the current task.

Print one line per address, including the address, the name of the function containing the address, and an estimate of its position within that function. Return nothing.

NOTE

it is recommended to use `print_usyms` instead of this function.

function::print_usyms

function::print_usyms — Print out user stack from string

Synopsis

```
print_usyms(callers:string)
```

Arguments

callers String with list of hexadecimal (user) addresses

Description

This function performs a symbolic lookup of the addresses in the given string, which are assumed to be the result of prior calls to `ustack`, `ucallers`, and similar functions.

Prints one line per address, including the address, the name of the function containing the address, and an estimate of its position within that function, as obtained by `usymdata`. Returns nothing.

function::probe_type

function::probe_type — The low level probe handler type of the current probe.

Synopsis

```
probe_type:string()
```

Arguments

None

Description

Returns a short string describing the low level probe handler type for the current probe point. This is for informational purposes only. Depending on the low level probe handler different context functions can or cannot provide information about the current event (for example some probe handlers only trigger in user space and have no associated kernel context). High-level probes might map to the same or different low-level probes (depending on systemtap version and/or kernel used).

function::probefunc

function::probefunc — Return the probe point's function name, if known

Synopsis

```
probefunc:string()
```

Arguments

None

Description

This function returns the name of the function being probed based on the current address, as computed by `symname(addr)` or `usymname(uaddr)` depending on probe context (whether the probe is a user probe or a kernel probe).

Please note

this function's behaviour differs between SystemTap 2.0 and earlier versions. Prior to 2.0, `probefunc` obtained the function name from the probe point string as returned by `pp`, and used the current address as a fallback.

function::probemod

function::probemod — Return the probe point's kernel module name

Synopsis

```
probemod:string()
```

Arguments

None

Description

This function returns the name of the kernel module containing the probe point, if known.

function::pstrace

function::pstrace — Chain of processes and pids back to init(1)

Synopsis

```
pstrace:string(task:long)
```

Arguments

task Pointer to task struct of process

Description

This function returns a string listing execname and pid for each process starting from *task* back to the process ancestor that init(1) spawned.

function::register

function::register — Return the signed value of the named CPU register

Synopsis

```
register:long(name:string)
```

Arguments

name Name of the register to return

Description

Return the value of the named CPU register, as it was saved when the current probe point was hit. If the register is 32 bits, it is sign-extended to 64 bits.

For the i386 architecture, the following names are recognized. (name1/name2 indicates that name1 and name2 are alternative names for the same register.) eax/ax, ebp/bp, ebx/bx, ecx/cx, edi/di, edx/dx, eflags flags, eip/ip, esi/si, esp/sp, orig_eax/orig_ax, xcs/cs, xds/ds, xes/es, xfs/fs, XSS/ss.

For the x86_64 architecture, the following names are recognized: 64-bit registers: r8, r9, r10, r11, r12, r13, r14, r15, rax/ax, rbp/bp, rbx/bx, rcx/cx, rdi/di, rdx/dx, rip/ip, rsi/si, rsp/sp; 32-bit registers: eax, ebp, ebx, ecx, edx, edi, edx, eip, esi, esp, flags/eflags, orig_eax; segment registers: xcs/cs, XSS/ss.

For powerpc, the following names are recognized: r0, r1, ... r31, nip, msr, orig_gpr3, ctr, link, xer, ccr, softc, trap, dar, dsisr, result.

For s390x, the following names are recognized: r0, r1, ... r15, args, psw.mask, psw.addr, orig_gpr2, ilc, trap.

function::registers_valid

function::registers_valid — Determines validity of register and u_register in current context

Synopsis

```
registers_valid:long( )
```

Arguments

None

Description

This function returns 1 if register and u_register can be used in the current context, or 0 otherwise. For example, registers_valid returns 0 when called from a begin or end probe.

function::regparm

function::regparm — Specify regparm value used to compile function

Synopsis

```
regparm(n:long)
```

Arguments

n original regparm value

Description

Call this function with argument *n* before accessing function arguments using the *_arg function if the function was build with the gcc -mregparm=*n* option.

(The i386 kernel is built with \-mregparm=3, so systemtap considers regparm(3) the default for kernel functions on that architecture.) Only valid on i386 and x86_64 (when probing 32bit applications). Produces an error on other architectures.

function::remote_id

function::remote_id — The index of this instance in a remote execution.

Synopsis

```
remote_id:long()
```

Arguments

None

Description

This function returns a number 0..N, which is the unique index of this particular script execution from a swarm of “stap --remote A --remote B ...” runs, and is the same number “stap --remote-prefix” would print. The function returns -1 if the script was not launched with “stap --remote”, or if the remote staprun/stapsh are older than version 1.7.

function::remote_uri

function::remote_uri — The name of this instance in a remote execution.

Synopsis

```
remote_uri:string()
```

Arguments

None

Description

This function returns the remote host used to invoke this particular script execution from a swarm of “stap --remote” runs. It may not be unique among the swarm. The function returns an empty string if the script was not launched with “stap --remote”.

function::s32_arg

function::s32_arg — Return function argument as signed 32-bit value

Synopsis

```
s32_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the signed 32-bit value of argument *n*, same as int_arg.

function::s64_arg

function::s64_arg — Return function argument as signed 64-bit value

Synopsis

```
s64_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the signed 64-bit value of argument *n*, same as longlong_arg.

function::sid

function::sid — Returns the session ID of the current process

Synopsis

```
sid:long()
```

Arguments

None

Description

The session ID of a process is the process group ID of the session leader. Session ID is stored in the signal_struct since Kernel 2.6.0.

function::sprint_backtrace

function::sprint_backtrace — Return stack back trace as string

Synopsis

```
sprint_backtrace:string()
```

Arguments

None

Description

Returns a simple (kernel) backtrace. One line per address. Includes the symbol name (or hex address if symbol couldn't be resolved) and module name (if found). Includes the offset from the start of the function if found, otherwise the offset will be added to the module (if found, between brackets). Returns the backtrace as string (each line terminated by a newline character). Note that the returned stack will be truncated to MAXSTRINGLEN, to print fuller and richer stacks use print_backtrace. Equivalent to sprint_stack(backtrace), but more efficient (no need to translate between hex strings and final backtrace string).

function::sprint_stack

function::sprint_stack — Return stack for kernel addresses from string

Synopsis

```
sprint_stack:string(stk:string)
```

Arguments

stk String with list of hexadecimal (kernel) addresses

Description

Perform a symbolic lookup of the addresses in the given string, which is assumed to be the result of a prior call to backtrace.

Returns a simple backtrace from the given hex string. One line per address. Includes the symbol name (or hex address if symbol couldn't be resolved) and module name (if found). Includes the offset from the start of the function if found, otherwise the offset will be added to the module (if found, between brackets). Returns the backtrace as string (each line terminated by a newline character). Note that the returned stack will be truncated to MAXSTRINGLEN, to print fuller and richer stacks use print_stack.

NOTE

it is recommended to use `sprint_syms` instead of this function.

function::sprint_syms

function::sprint_syms — Return stack for kernel addresses from string

Synopsis

```
sprint_syms(callers:string)
```

Arguments

callers String with list of hexadecimal (kernel) addresses

Description

Perform a symbolic lookup of the addresses in the given string, which are assumed to be the result of a prior calls to `stack`, `callers`, and similar functions.

Returns a simple backtrace from the given hex string. One line per address. Includes the symbol name (or hex address if symbol couldn't be resolved) and module name (if found), as obtained from `sym-data`. Includes the offset from the start of the function if found, otherwise the offset will be added to the module (if found, between brackets). Returns the backtrace as string (each line terminated by a newline character). Note that the returned stack will be truncated to `MAXSTRINGLEN`, to print fuller and richer stacks use `print_syms`.

function::sprint_ubacktrace

function::sprint_ubacktrace — Return stack back trace for current user-space task as string.

Synopsis

```
sprint_ubacktrace:string()
```

Arguments

None

Description

Returns a simple backtrace for the current task. One line per address. Includes the symbol name (or hex address if symbol couldn't be resolved) and module name (if found). Includes the offset from the start of the function if found, otherwise the offset will be added to the module (if found, between brackets). Returns the backtrace as string (each line terminated by a newline character). Note that the returned stack will be truncated to MAXSTRINGLEN, to print fuller and richer stacks use `print_ubacktrace`. Equivalent to `sprint_ustack(ubacktrace)`, but more efficient (no need to translate between hex strings and final backtrace string).

Note

To get (full) backtraces for user space applications and shared shared libraries not mentioned in the current script run `stap` with `-d /path/to/exe-or-so` and/or add `--ldd` to load all needed unwind data.

function::sprint_ustack

function::sprint_ustack — Return stack for the current task from string.

Synopsis

```
sprint_ustack:string(stk:string)
```

Arguments

stk String with list of hexadecimal addresses for the current task.

Description

Perform a symbolic lookup of the addresses in the given string, which is assumed to be the result of a prior call to `ubacktrace` for the current task.

Returns a simple backtrace from the given hex string. One line per address. Includes the symbol name (or hex address if symbol couldn't be resolved) and module name (if found). Includes the offset from the start of the function if found, otherwise the offset will be added to the module (if found, between brackets). Returns the backtrace as string (each line terminated by a newline character). Note that the returned stack will be truncated to `MAXSTRINGLEN`, to print fuller and richer stacks use `print_ustack`.

NOTE

it is recommended to use `sprint_usyms` instead of this function.

function::sprint_usyms

function::sprint_usyms — Return stack for user addresses from string

Synopsis

```
sprint_usyms(callers:string)
```

Arguments

callers String with list of hexadecimal (user) addresses

Description

Perform a symbolic lookup of the addresses in the given string, which are assumed to be the result of a prior calls to `ustack`, `ucallers`, and similar functions.

Returns a simple backtrace from the given hex string. One line per address. Includes the symbol name (or hex address if symbol couldn't be resolved) and module name (if found), as obtained from `usym-data`. Includes the offset from the start of the function if found, otherwise the offset will be added to the module (if found, between brackets). Returns the backtrace as string (each line terminated by a newline character). Note that the returned stack will be truncated to `MAXSTRINGLEN`, to print fuller and richer stacks use `print_usyms`.

function::stack

function::stack — Return address at given depth of kernel stack backtrace

Synopsis

```
stack:long(n:long)
```

Arguments

n number of levels to descend in the stack.

Description

Performs a simple (kernel) backtrace, and returns the element at the specified position. The results of the backtrace itself are cached, so that the backtrace computation is performed at most once no matter how many times `stack` is called, or in what order.

function::stack_size

function::stack_size — Return the size of the kernel stack

Synopsis

```
stack_size:long()
```

Arguments

None

Description

This function returns the size of the kernel stack.

function::stack_unused

function::stack_unused — Returns the amount of kernel stack currently available

Synopsis

```
stack_unused:long()
```

Arguments

None

Description

This function determines how many bytes are currently available in the kernel stack.

function::stack_used

function::stack_used — Returns the amount of kernel stack used

Synopsis

```
stack_used:long()
```

Arguments

None

Description

This function determines how many bytes are currently used in the kernel stack.

function::stp_pid

function::stp_pid — The process id of the stapio process

Synopsis

```
stp_pid:long()
```

Arguments

None

Description

This function returns the process id of the stapio process that launched this script. There could be other SystemTap scripts and stapio processes running on the system.

function::syndata

function::syndata — Return the kernel symbol and module offset for the address

Synopsis

```
syndata:string(addr:long)
```

Arguments

addr The address to translate

Description

Returns the (function) symbol name associated with the given address if known, the offset from the start and size of the symbol, plus module name (between brackets). If symbol is unknown, but module is known, the offset inside the module, plus the size of the module is added. If any element is not known it will be omitted and if the symbol name is unknown it will return the hex string for the given address.

function::symname

function::symname — Return the kernel symbol associated with the given address

Synopsis

```
symname:string(addr:long)
```

Arguments

addr The address to translate

Description

Returns the (function) symbol name associated with the given address if known. If not known it will return the hex string representation of *addr*.

function::target

function::target — Return the process ID of the target process

Synopsis

```
target:long( )
```

Arguments

None

Description

This function returns the process ID of the target process. This is useful in conjunction with the -x PID or -c CMD command-line options to stap. An example of its use is to create scripts that filter on a specific process.

-x <pid> target returns the pid specified by -x

-c <command> target returns the pid for the executed command specified by -c

function::task_backtrace

function::task_backtrace — Hex backtrace of an arbitrary task

Synopsis

```
task_backtrace:string(task:long)
```

Arguments

task pointer to task_struct

Description

This function returns a string of hex addresses that are a backtrace of the stack of a particular task
Output may be truncated as per maximum string length. Deprecated in SystemTap 1.6.

function::task_cpu

function::task_cpu — The scheduled cpu of the task

Synopsis

```
task_cpu:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the scheduled cpu for the given task.

function::task_current

function::task_current — The current task_struct of the current task

Synopsis

```
task_current:long()
```

Arguments

None

Description

This function returns the task_struct representing the current process. This address can be passed to the various task_*() functions to extract more task-specific data.

function::task_egid

function::task_egid — The effective group identifier of the task

Synopsis

```
task_egid:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the effective group id of the given task.

function::task_euid

function::task_euid — The effective user identifier of the task

Synopsis

```
task_euid:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the effective user id of the given task.

function::task_execname

function::task_execname — The name of the task

Synopsis

```
task_execname:string(task:long)
```

Arguments

task task_struct pointer

Description

Return the name of the given task.

function::task_gid

function::task_gid — The group identifier of the task

Synopsis

```
task_gid:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the group id of the given task.

function::task_max_file_handles

function::task_max_file_handles — The max number of open files for the task

Synopsis

```
task_max_file_handles:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the maximum number of file handlers for the given task.

function::task_nice

function::task_nice — The nice value of the task

Synopsis

```
task_nice:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the nice value of the given task.

function::task_open_file_handles

function::task_open_file_handles — The number of open files of the task

Synopsis

```
task_open_file_handles:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the number of open file handlers for the given task.

function::task_parent

function::task_parent — The task_struct of the parent task

Synopsis

```
task_parent:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the parent task_struct of the given task. This address can be passed to the various task_*() functions to extract more task-specific data.

function::task_pid

function::task_pid — The process identifier of the task

Synopsis

```
task_pid:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the process id of the given task.

function::task_prio

function::task_prio — The priority value of the task

Synopsis

```
task_prio:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the priority value of the given task.

function::task_state

function::task_state — The state of the task

Synopsis

```
task_state:long(task:long)
```

Arguments

task task_struct pointer

Description

Return the state of the given task, one of: TASK_RUNNING (0), TASK_INTERRUPTIBLE (1), TASK_UNINTERRUPTIBLE (2), TASK_STOPPED (4), TASK_TRACED (8), EXIT_ZOMBIE (16), or EXIT_DEAD (32).

function::task_tid

function::task_tid — The thread identifier of the task

Synopsis

```
task_tid:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the thread id of the given task.

function::task_uid

function::task_uid — The user identifier of the task

Synopsis

```
task_uid:long(task:long)
```

Arguments

task task_struct pointer

Description

This function returns the user id of the given task.

function::tid

function::tid — Returns the thread ID of a target process

Synopsis

```
tid:long()
```

Arguments

None

Description

This function returns the thread ID of the target process.

function::u32_arg

function::u32_arg — Return function argument as unsigned 32-bit value

Synopsis

```
u32_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the unsigned 32-bit value of argument *n*, same as uint_arg.

function::u64_arg

function::u64_arg — Return function argument as unsigned 64-bit value

Synopsis

```
u64_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the unsigned 64-bit value of argument *n*, same as ulonglong_arg.

function::u_register

function::u_register — Return the unsigned value of the named CPU register

Synopsis

```
u_register:long(name:string)
```

Arguments

name Name of the register to return

Description

Same as register(*name*), except that if the register is 32 bits wide, it is zero-extended to 64 bits.

function::uaddr

function::uaddr — User space address of current running task

Synopsis

```
uaddr:long()
```

Arguments

None

Description

Returns the address in userspace that the current task was at when the probe occurred. When the current running task isn't a user space thread, or the address cannot be found, zero is returned. Can be used to see where the current task is combined with usymname or usymdata. Often the task will be in the VDSO where it entered the kernel.

function::ubacktrace

function::ubacktrace — Hex backtrace of current user-space task stack.

Synopsis

```
ubacktrace:string()
```

Arguments

None

Description

Return a string of hex addresses that are a backtrace of the stack of the current task. Output may be truncated as per maximum string length. Returns empty string when current probe point cannot determine user backtrace. See `backtrace` for kernel traceback.

Note

To get (full) backtraces for user space applications and shared shared libraries not mentioned in the current script run `stap` with `-d /path/to/exe-or-so` and/or add `--ldd` to load all needed unwind data.

function::ucallers

function::ucallers — Return first n elements of user stack backtrace

Synopsis

```
ucallers:string(n:long)
```

Arguments

n number of levels to descend in the stack (not counting the top level). If *n* is -1, print the entire stack.

Description

This function returns a string of the first *n* hex addresses from the backtrace of the user stack. Output may be truncated as per maximum string length (MAXSTRINGLEN).

Note

To get (full) backtraces for user space applications and shared shared libraries not mentioned in the current script run stap with -d /path/to/exe-or-so and/or add --ldd to load all needed unwind data.

function::uid

function::uid — Returns the user ID of a target process

Synopsis

```
uid:long()
```

Arguments

None

Description

This function returns the user ID of the target process.

function::uint_arg

function::uint_arg — Return function argument as unsigned int

Synopsis

```
uint_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the value of argument *n* as an unsigned int (i.e., a 32-bit integer zero-extended to 64 bits).

function::ulong_arg

function::ulong_arg — Return function argument as unsigned long

Synopsis

```
ulong_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the value of argument *n* as an unsigned long. On architectures where a long is 32 bits, the value is zero-extended to 64 bits.

function::ulonglong_arg

function::ulonglong_arg — Return function argument as 64-bit value

Synopsis

```
ulonglong_arg:long(n:long)
```

Arguments

n index of argument to return

Description

Return the value of argument *n* as a 64-bit value. (Same as longlong_arg.)

function::umodname

function::umodname — Returns the (short) name of the user module.

Synopsis

```
umodname:string(addr:long)
```

Arguments

addr User-space address

Description

Returns the short name of the user space module for the current task that that the given address is part of. Reports an error when the address isn't in a (mapped in) module, or the module cannot be found for some reason.

function::user_mode

function::user_mode — Determines if probe point occurs in user-mode

Synopsis

```
user_mode:long( )
```

Arguments

None

Description

Return 1 if the probe point occurred in user-mode.

function::ustack

function::ustack — Return address at given depth of user stack backtrace

Synopsis

```
ustack:long(n:long)
```

Arguments

n number of levels to descend in the stack.

Description

Performs a simple (user space) backtrace, and returns the element at the specified position. The results of the backtrace itself are cached, so that the backtrace computation is performed at most once no matter how many times `ustack` is called, or in what order.

function::usymdata

function::usymdata — Return the symbol and module offset of an address.

Synopsis

```
usymdata:string(addr:long)
```

Arguments

addr The address to translate.

Description

Returns the (function) symbol name associated with the given address in the current task if known, the offset from the start and the size of the symbol, plus the module name (between brackets). If symbol is unknown, but module is known, the offset inside the module, plus the size of the module is added. If any element is not known it will be omitted and if the symbol name is unknown it will return the hex string for the given address.

function::usymname

function::usymname — Return the symbol of an address in the current task.

Synopsis

```
usymname:string(addr:long)
```

Arguments

addr The address to translate.

Description

Returns the (function) symbol name associated with the given address if known. If not known it will return the hex string representation of *addr*.

Chapter 3. Timestamp Functions

Each timestamp function returns a value to indicate when a function is executed. These returned values can then be used to indicate when an event occurred, provide an ordering for events, or compute the amount of time elapsed between two time stamps.

function::HZ

function::HZ — Kernel HZ

Synopsis

```
HZ:long( )
```

Arguments

None

Description

This function returns the value of the kernel HZ macro, which corresponds to the rate of increase of the jiffies value.

function::cpu_clock_ms

function::cpu_clock_ms — Number of milliseconds on the given cpu's clock

Synopsis

```
cpu_clock_ms:long(cpu:long)
```

Arguments

cpu Which processor's clock to read

Description

This function returns the number of milliseconds on the given cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::cpu_clock_ns

function::cpu_clock_ns — Number of nanoseconds on the given cpu's clock

Synopsis

```
cpu_clock_ns:long(cpu:long)
```

Arguments

cpu Which processor's clock to read

Description

This function returns the number of nanoseconds on the given cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::cpu_clock_s

function::cpu_clock_s — Number of seconds on the given cpu's clock

Synopsis

```
cpu_clock_s:long(cpu:long)
```

Arguments

cpu Which processor's clock to read

Description

This function returns the number of seconds on the given cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::cpu_clock_us

function::cpu_clock_us — Number of microseconds on the given cpu's clock

Synopsis

```
cpu_clock_us:long(cpu:long)
```

Arguments

cpu Which processor's clock to read

Description

This function returns the number of microseconds on the given cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::delete_stopwatch

function::delete_stopwatch — Remove an existing stopwatch

Synopsis

```
delete_stopwatch(name:string)
```

Arguments

name the stopwatch name

Description

Remove stopwatch *name*.

function::get_cycles

function::get_cycles — Processor cycle count

Synopsis

```
get_cycles:long()
```

Arguments

None

Description

This function returns the processor cycle counter value if available, else it returns zero. The cycle counter is free running and unsynchronized on each processor. Thus, the order of events cannot be determined by comparing the results of the get_cycles function on different processors.

function::gettimeofday_ms

function::gettimeofday_ms — Number of milliseconds since UNIX epoch

Synopsis

```
gettimeofday_ms:long( )
```

Arguments

None

Description

This function returns the number of milliseconds since the UNIX epoch.

function:: gettimeofday_ns

function:: gettimeofday_ns — Number of nanoseconds since UNIX epoch

Synopsis

```
gettimeofday_ns:long( )
```

Arguments

None

Description

This function returns the number of nanoseconds since the UNIX epoch.

function:: gettimeofday_s

function:: gettimeofday_s — Number of seconds since UNIX epoch

Synopsis

```
gettimeofday_s:long( )
```

Arguments

None

Description

This function returns the number of seconds since the UNIX epoch.

function:: gettimeofday_us

function:: gettimeofday_us — Number of microseconds since UNIX epoch

Synopsis

```
gettimeofday_us:long( )
```

Arguments

None

Description

This function returns the number of microseconds since the UNIX epoch.

function::jiffies

function::jiffies — Kernel jiffies count

Synopsis

```
jiffies:long()
```

Arguments

None

Description

This function returns the value of the kernel jiffies variable. This value is incremented periodically by timer interrupts, and may wrap around a 32-bit or 64-bit boundary. See HZ.

function::local_clock_ms

function::local_clock_ms — Number of milliseconds on the local cpu's clock

Synopsis

```
local_clock_ms:long( )
```

Arguments

None

Description

This function returns the number of milliseconds on the local cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::local_clock_ns

function::local_clock_ns — Number of nanoseconds on the local cpu's clock

Synopsis

```
local_clock_ns:long( )
```

Arguments

None

Description

This function returns the number of nanoseconds on the local cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::local_clock_s

function::local_clock_s — Number of seconds on the local cpu's clock

Synopsis

```
local_clock_s:long( )
```

Arguments

None

Description

This function returns the number of seconds on the local cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::local_clock_us

function::local_clock_us — Number of microseconds on the local cpu's clock

Synopsis

```
local_clock_us:long( )
```

Arguments

None

Description

This function returns the number of microseconds on the local cpu's clock. This is always monotonic comparing on the same cpu, but may have some drift between cpus (within about a jiffy).

function::read_stopwatch_ms

function::read_stopwatch_ms — Reads the time in milliseconds for a stopwatch

Synopsis

```
read_stopwatch_ms:long(name:string)
```

Arguments

name stopwatch name

Description

Returns time in milliseconds for stopwatch *name*. Creates stopwatch *name* if it does not currently exist.

function::read_stopwatch_ns

function::read_stopwatch_ns — Reads the time in nanoseconds for a stopwatch

Synopsis

```
read_stopwatch_ns:long(name:string)
```

Arguments

name stopwatch name

Description

Returns time in nanoseconds for stopwatch *name*. Creates stopwatch *name* if it does not currently exist.

function::read_stopwatch_s

function::read_stopwatch_s — Reads the time in seconds for a stopwatch

Synopsis

```
read_stopwatch_s:long(name:string)
```

Arguments

name stopwatch name

Description

Returns time in seconds for stopwatch *name*. Creates stopwatch *name* if it does not currently exist.

function::read_stopwatch_us

function::read_stopwatch_us — Reads the time in microseconds for a stopwatch

Synopsis

```
read_stopwatch_us:long(name:string)
```

Arguments

name stopwatch name

Description

Returns time in microseconds for stopwatch *name*. Creates stopwatch *name* if it does not currently exist.

function::start_stopwatch

function::start_stopwatch — Start a stopwatch

Synopsis

```
start_stopwatch(name:string)
```

Arguments

name the stopwatch name

Description

Start stopwatch *name*. Creates stopwatch *name* if it does not currently exist.

function::stop_stopwatch

function::stop_stopwatch — Stop a stopwatch

Synopsis

```
stop_stopwatch(name:string)
```

Arguments

name the stopwatch name

Description

Stop stopwatch *name*. Creates stopwatch *name* if it does not currently exist.

Chapter 4. Time utility functions

Utility functions to turn seconds since the epoch (as returned by the timestamp function `gettimeofday_s()`) into a human readable date/time strings.

function::ctime

function::ctime — Convert seconds since epoch into human readable date/time string

Synopsis

```
ctime:string(epochsecs:long)
```

Arguments

epochsecs Number of seconds since epoch (as returned by `gettimeofday_s`)

Description

Takes an argument of seconds since the epoch as returned by `gettimeofday_s`. Returns a string of the form

“Wed Jun 30 21:49:08 1993”

The string will always be exactly 24 characters. If the time would be unreasonable far in the past (before what can be represented with a 32 bit offset in seconds from the epoch) an error will occur (which can be avoided with try/catch). If the time would be unreasonable far in the future, an error will also occur.

Note that the epoch (zero) corresponds to

“Thu Jan 1 00:00:00 1970”

The earliest full date given by ctime, corresponding to epochsecs -2147483648 is “Fri Dec 13 20:45:52 1901”. The latest full date given by ctime, corresponding to epochsecs 2147483647 is “Tue Jan 19 03:14:07 2038”.

The abbreviations for the days of the week are ‘Sun’, ‘Mon’, ‘Tue’, ‘Wed’, ‘Thu’, ‘Fri’, and ‘Sat’. The abbreviations for the months are ‘Jan’, ‘Feb’, ‘Mar’, ‘Apr’, ‘May’, ‘Jun’, ‘Jul’, ‘Aug’, ‘Sep’, ‘Oct’, ‘Nov’, and ‘Dec’.

Note that the real C library `ctime` function puts a newline ('\n') character at the end of the string that this function does not. Also note that since the kernel has no concept of timezones, the returned time is always in GMT.

function::tz_ctime

function::tz_ctime — Convert seconds since epoch into human readable date/time string, with local time zone

Synopsis

```
tz_ctime(epochsecs:)
```

Arguments

epochsecs number of seconds since epoch (as returned by `gettimeofday_s`)

Description

Takes an argument of seconds since the epoch as returned by `gettimeofday_s`. Returns a string of the same form as `ctime`, but offsets the epoch time for the local time zone, and appends the name of the local time zone. The string length may vary. The time zone information is passed by `staprun` at script startup only.

function::tz_gmtoff

function::tz_gmtoff — Return local time zone offset

Synopsis

```
tz_gmtoff()
```

Arguments

None

Description

Returns the local time zone offset (seconds west of UTC), as passed by `staprund` at script startup only.

function::tz_name

function::tz_name — Return local time zone name

Synopsis

```
tz_name( )
```

Arguments

None

Description

Returns the local time zone name, as passed by `staprun` at script startup only.

Chapter 5. Shell command functions

Utility functions to enqueue shell commands.

function::system

function::system — Issue a command to the system

Synopsis

```
system(cmd:string)
```

Arguments

cmd the command to issue to the system

Description

This function runs a command on the system. The command is started in the background some time after the current probe completes. The command is run with the same UID as the user running the stап or старун command.

Chapter 6. Memory Tapset

This family of probe points is used to probe memory-related events or query the memory usage of the current process. It contains the following probe points:

function::addr_to_node

function::addr_to_node — Returns which node a given address belongs to within a NUMA system

Synopsis

```
addr_to_node:long(addr:long)
```

Arguments

addr the address of the faulting memory access

Description

This function accepts an address, and returns the node that the given address belongs to in a NUMA system.

function::bytes_to_string

function::bytes_to_string — Human readable string for given bytes

Synopsis

```
bytes_to_string:string(bytes:long)
```

Arguments

bytes Number of bytes to translate.

Description

Returns a string representing the number of bytes (up to 1024 bytes), the number of kilobytes (when less than 1024K) postfixed by 'K', the number of megabytes (when less than 1024M) postfixed by 'M' or the number of gigabytes postfixed by 'G'. If representing K, M or G, and the number is amount is less than 100, it includes a '.' plus the remainder. The returned string will be 5 characters wide (padding with whitespace at the front) unless negative or representing more than 9999G bytes.

function::mem_page_size

function::mem_page_size — Number of bytes in a page for this architecture

Synopsis

```
mem_page_size:long( )
```

Arguments

None

function::pages_to_string

function::pages_to_string — Turns pages into a human readable string

Synopsis

```
pages_to_string:string(pages:long)
```

Arguments

pages Number of pages to translate.

Description

Multiplies pages by page_size to get the number of bytes and returns the result of bytes_to_string.

function::proc_mem_data

function::proc_mem_data — Program data size (data + stack) in pages

Synopsis

```
proc_mem_data:long( )
```

Arguments

None

Description

Returns the current process data size (data + stack) in pages, or zero when there is no current process or the number of pages couldn't be retrieved.

function::proc_mem_data_pid

function::proc_mem_data_pid — Program data size (data + stack) in pages

Synopsis

```
proc_mem_data_pid:long(pid:long)
```

Arguments

pid The pid of process to examine

Description

Returns the given process data size (data + stack) in pages, or zero when the process doesn't exist or the number of pages couldn't be retrieved.

function::proc_mem_rss

function::proc_mem_rss — Program resident set size in pages

Synopsis

```
proc_mem_rss:long()
```

Arguments

None

Description

Returns the resident set size in pages of the current process, or zero when there is no current process or the number of pages couldn't be retrieved.

function::proc_mem_rss_pid

function::proc_mem_rss_pid — Program resident set size in pages

Synopsis

```
proc_mem_rss_pid:long(pid:long)
```

Arguments

pid The pid of process to examine

Description

Returns the resident set size in pages of the given process, or zero when the process doesn't exist or the number of pages couldn't be retrieved.

function::proc_mem_shr

function::proc_mem_shr — Program shared pages (from shared mappings)

Synopsis

```
proc_mem_shr:long()
```

Arguments

None

Description

Returns the shared pages (from shared mappings) of the current process, or zero when there is no current process or the number of pages couldn't be retrieved.

function::proc_mem_shr_pid

function::proc_mem_shr_pid — Program shared pages (from shared mappings)

Synopsis

```
proc_mem_shr_pid:long(pid:long)
```

Arguments

pid The pid of process to examine

Description

Returns the shared pages (from shared mappings) of the given process, or zero when the process doesn't exist or the number of pages couldn't be retrieved.

function::proc_mem_size

function::proc_mem_size — Total program virtual memory size in pages

Synopsis

```
proc_mem_size:long( )
```

Arguments

None

Description

Returns the total virtual memory size in pages of the current process, or zero when there is no current process or the number of pages couldn't be retrieved.

function::proc_mem_size_pid

function::proc_mem_size_pid — Total program virtual memory size in pages

Synopsis

```
proc_mem_size_pid:long(pid:long)
```

Arguments

pid The pid of process to examine

Description

Returns the total virtual memory size in pages of the given process, or zero when that process doesn't exist or the number of pages couldn't be retrieved.

function::proc_mem_string

function::proc_mem_string — Human readable string of current proc memory usage

Synopsis

```
proc_mem_string:string()
```

Arguments

None

Description

Returns a human readable string showing the size, rss, shr, txt and data of the memory used by the current process. For example “size: 301m, rss: 11m, shr: 8m, txt: 52k, data: 2248k”.

function::proc_mem_string_pid

function::proc_mem_string_pid — Human readable string of process memory usage

Synopsis

```
proc_mem_string_pid:string(pid:long)
```

Arguments

pid The pid of process to examine

Description

Returns a human readable string showing the size, rss, shr, txt and data of the memory used by the given process. For example “size: 301m, rss: 11m, shr: 8m, txt: 52k, data: 2248k”.

function::proc_mem_txt

function::proc_mem_txt — Program text (code) size in pages

Synopsis

```
proc_mem_txt:long()
```

Arguments

None

Description

Returns the current process text (code) size in pages, or zero when there is no current process or the number of pages couldn't be retrieved.

function::proc_mem_txt_pid

function::proc_mem_txt_pid — Program text (code) size in pages

Synopsis

```
proc_mem_txt_pid:long(pid:long)
```

Arguments

pid The pid of process to examine

Description

Returns the given process text (code) size in pages, or zero when the process doesn't exist or the number of pages couldn't be retrieved.

function::vm_fault_contains

function::vm_fault_contains — Test return value for page fault reason

Synopsis

```
vm_fault_contains:long(value:long,test:long)
```

Arguments

value the fault_type returned by vm.page_fault.return

test the type of fault to test for (VM_FAULT_OOM or similar)

probe::vm.brk

probe::vm.brk — Fires when a brk is requested (i.e. the heap will be resized)

Synopsis

vm.brk

Values

address the requested address

name name of the probe point

length the length of the memory segment

Context

The process calling brk.

probe::vm.kfree

probe::vm.kfree — Fires when kfree is requested

Synopsis

vm.kfree

Values

<i>ptr</i>	pointer to the kmemory allocated which is returned by kmalloc
<i>name</i>	name of the probe point
<i>call_site</i>	address of the function calling this kmemory function
<i>caller_function</i>	name of the caller function.

probe::vm.kmalloc

probe::vm.kmalloc — Fires when kmalloc is requested

Synopsis

vm.kmalloc

Values

<i>bytes_alloc</i>	allocated Bytes
<i>caller_function</i>	name of the caller function
<i>call_site</i>	address of the kmemory function
<i>name</i>	name of the probe point
<i>gfp_flags</i>	type of kmemory to allocate
<i>bytes_req</i>	requested Bytes
<i>gfp_flag_name</i>	type of kmemory to allocate (in String format)
<i>ptr</i>	pointer to the kmemory allocated

probe::vm.kmalloc_node

probe::vm.kmalloc_node — Fires when kmalloc_node is requested

Synopsis

vm.kmalloc_node

Values

<i>gfp_flag_name</i>	type of kmemory to allocate(in string format)
<i>ptr</i>	pointer to the kmemory allocated
<i>gfp_flags</i>	type of kmemory to allocate
<i>bytes_req</i>	requested Bytes
<i>name</i>	name of the probe point
<i>caller_function</i>	name of the caller function
<i>call_site</i>	address of the function caling this kmemory function
<i>bytes_alloc</i>	allocated Bytes

probe::vm.kmem_cache_alloc

probe::vm.kmem_cache_alloc — Fires when kmem_cache_alloc is requested

Synopsis

vm.kmem_cache_alloc

Values

<i>gfp_flag_name</i>	type of kmemory to allocate(in string format)
<i>ptr</i>	pointer to the kmemory allocated
<i>gfp_flags</i>	type of kmemory to allocate
<i>bytes_req</i>	requested Bytes
<i>name</i>	name of the probe point
<i>caller_function</i>	name of the caller function.
<i>call_site</i>	address of the function calling this kmemory function.
<i>bytes_alloc</i>	allocated Bytes

probe::vm.kmem_cache_alloc_node

probe::vm.kmem_cache_alloc_node — Fires when kmem_cache_alloc_node is requested

Synopsis

vm.kmem_cache_alloc_node

Values

<i>name</i>	name of the probe point
<i>call_site</i>	address of the function calling this kmemory function
<i>caller_function</i>	name of the caller function
<i>bytes_alloc</i>	allocated Bytes
<i>ptr</i>	pointer to the kmemory allocated
<i>gfp_flag_name</i>	type of kmemory to allocate(in string format)
<i>bytes_req</i>	requested Bytes
<i>gfp_flags</i>	type of kmemory to allocate

probe::vm.kmem_cache_free

probe::vm.kmem_cache_free — Fires when kmem_cache_free is requested

Synopsis

`vm.kmem_cache_free`

Values

<i>name</i>	Name of the probe point
<i>call_site</i>	Address of the function calling this kmemory function
<i>caller_function</i>	Name of the caller function.
<i>ptr</i>	Pointer to the kmemory allocated which is returned by kmem_cache

probe::vm.mmap

probe::vm.mmap — Fires when an mmap is requested

Synopsis

`vm.mmap`

Values

name name of the probe point

length the length of the memory segment

address the requested address

Context

The process calling mmap.

probe::vm.munmap

probe::vm.munmap — Fires when an munmap is requested

Synopsis

`vm.munmap`

Values

length the length of the memory segment

name name of the probe point

address the requested address

Context

The process calling munmap.

probe::vm.oom_kill

probe::vm.oom_kill — Fires when a thread is selected for termination by the OOM killer

Synopsis

`vm.oom_kill`

Values

task the task being killed

name name of the probe point

Context

The process that tried to consume excessive memory, and thus triggered the OOM.

probe::vm.pagefault

probe::vm.pagefault — Records that a page fault occurred

Synopsis

`vm.pagefault`

Values

<i>name</i>	name of the probe point
<i>address</i>	the address of the faulting memory access; i.e. the address that caused the page fault
<i>write_access</i>	indicates whether this was a write or read access; 1 indicates a write, while 0 indicates a read

Context

The process which triggered the fault

probe::vm.pagefault.return

probe::vm.pagefault.return — Indicates what type of fault occurred

Synopsis

```
vm.pagefault.return
```

Values

fault_type returns either 0 (VM_FAULT_OOM) for out of memory faults, 2 (VM_FAULT_MINOR) for minor faults, 3 (VM_FAULT_MAJOR) for major faults, or 1 (VM_FAULT_SIGBUS) if the fault was neither OOM, minor fault, nor major fault.

<i>name</i>	name of the probe point
-------------	-------------------------

probe::vm.write_shared

probe::vm.write_shared — Attempts at writing to a shared page

Synopsis

`vm.write_shared`

Values

name name of the probe point

address the address of the shared write

Context

The context is the process attempting the write.

Description

Fires when a process attempts to write to a shared page. If a copy is necessary, this will be followed by a `vm.write_shared_copy`.

probe::vm.write_shared_copy

probe::vm.write_shared_copy — Page copy for shared page write

Synopsis

`vm.write_shared_copy`

Values

name Name of the probe point

zero boolean indicating whether it is a zero page (can do a clear instead of a copy)

address The address of the shared write

Context

The process attempting the write.

Description

Fires when a write to a shared page requires a page copy. This is always preceded by a `vm.write_shared`.

Chapter 7. Task Time Tapset

This tapset defines utility functions to query time related properties of the current tasks, translate those in milliseconds and human readable strings.

function::cputime_to_msecs

function::cputime_to_msecs — Translates the given cputime into milliseconds

Synopsis

```
cputime_to_msecs:long(cputime:long)
```

Arguments

cputime Time to convert to milliseconds.

function::cputime_to_string

function::cputime_to_string — Human readable string for given cputime

Synopsis

```
cputime_to_string:string(cputime:long)
```

Arguments

cputime Time to translate.

Description

Equivalent to calling: msec_to_string (cputime_to_msecs (cputime)).

function::cputime_to_usecs

function::cputime_to_usecs — Translates the given cputime into microseconds

Synopsis

```
cputime_to_usecs:long(cputime:long)
```

Arguments

cputime Time to convert to microseconds.

function::msecs_to_string

function::msecs_to_string — Human readable string for given milliseconds

Synopsis

```
msecs_to_string:string(msecs:long)
```

Arguments

msecs Number of milliseconds to translate.

Description

Returns a string representing the number of milliseconds as a human readable string consisting of “XmY.ZZZs”, where X is the number of minutes, Y is the number of seconds and ZZZ is the number of milliseconds.

function::task_stime

function::task_stime — System time of the current task

Synopsis

```
task_stime:long()
```

Arguments

None

Description

Returns the system time of the current task in cputime. Does not include any time used by other tasks in this process, nor does it include any time of the children of this task.

function::task_stime_tid

function::task_stime_tid — System time of the given task

Synopsis

```
task_stime_tid:long(tid:long)
```

Arguments

tid Thread id of the given task

Description

Returns the system time of the given task in cputime, or zero if the task doesn't exist. Does not include any time used by other tasks in this process, nor does it include any time of the children of this task.

function::task_time_string

function::task_time_string — Human readable string of task time usage

Synopsis

```
task_time_string:string()
```

Arguments

None

Description

Returns a human readable string showing the user and system time the current task has used up to now. For example “usr: 0m12.908s, sys: 1m6.851s”.

function::task_time_string_tid

function::task_time_string_tid — Human readable string of task time usage

Synopsis

```
task_time_string_tid:string(tid:long)
```

Arguments

tid Thread id of the given task

Description

Returns a human readable string showing the user and system time the given task has used up to now.
For example “usr: 0m12.908s, sys: 1m6.851s”.

function::task_utime

function::task_utime — User time of the current task

Synopsis

```
task_utime:long()
```

Arguments

None

Description

Returns the user time of the current task in cputime. Does not include any time used by other tasks in this process, nor does it include any time of the children of this task.

function::task_utime_tid

function::task_utime_tid — User time of the given task

Synopsis

```
task_utime_tid:long(tid:long)
```

Arguments

tid Thread id of the given task

Description

Returns the user time of the given task in cputime, or zero if the task doesn't exist. Does not include any time used by other tasks in this process, nor does it include any time of the children of this task.

function::usecs_to_string

function::usecs_to_string — Human readable string for given microseconds

Synopsis

```
usecs_to_string:string(usecs:long)
```

Arguments

usecs Number of microseconds to translate.

Description

Returns a string representing the number of milliseconds as a human readable string consisting of “XmY.ZZZZZZs”, where X is the number of minutes, Y is the number of seconds and ZZZZZZ is the number of microseconds.

Chapter 8. Scheduler Tapset

This family of probe points is used to probe the task scheduler activities. It contains the following probe points:

probe::scheduler.balance

probe::scheduler.balance — A cpu attempting to find more work.

Synopsis

```
scheduler.balance
```

Values

name name of the probe point

Context

The cpu looking for more work.

probe::scheduler.cpu_off

probe::scheduler.cpu_off — Process is about to stop running on a cpu

Synopsis

```
scheduler.cpu_off
```

Values

<i>name</i>	name of the probe point
<i>task_prev</i>	the process leaving the cpu (same as current)
<i>task_next</i>	the process replacing current
<i>idle</i>	boolean indicating whether current is the idle process

Context

The process leaving the cpu.

probe::scheduler.cpu_on

probe::scheduler.cpu_on — Process is beginning execution on a cpu

Synopsis

```
scheduler.cpu_on
```

Values

name name of the probe point

task_prev the process that was previously running on this cpu

idle - boolean indicating whether current is the idle process

Context

The resuming process.

probe::scheduler.ctxswitch

probe::scheduler.ctxswitch — A context switch is occurring.

Synopsis

```
scheduler.ctxswitch
```

Values

<i>nexttsk_state</i>	the state of the process to be switched in
<i>prev_pid</i>	The PID of the process to be switched out
<i>prevtsk_state</i>	the state of the process to be switched out
<i>next_priority</i>	The priority of the process to be switched in
<i>prev_task_name</i>	The name of the process to be switched out
<i>next_tid</i>	The TID of the process to be switched in
<i>name</i>	name of the probe point
<i>prev_tid</i>	The TID of the process to be switched out
<i>next_task_name</i>	The name of the process to be switched in
<i>next_pid</i>	The PID of the process to be switched in
<i>prev_priority</i>	The priority of the process to be switched out

probe::scheduler.kthread_stop

probe::scheduler.kthread_stop — A thread created by kthread_create is being stopped

Synopsis

```
scheduler.kthread_stop
```

Values

thread_pid PID of the thread being stopped

thread_priority priority of the thread

probe::scheduler.kthread_stop.return

probe::scheduler.kthread_stop.return — A kthread is stopped and gets the return value

Synopsis

```
scheduler.kthread_stop.return
```

Values

return_value return value after stopping the thread

name name of the probe point

probe::scheduler.migrate

probe::scheduler.migrate — Task migrating across cpus

Synopsis

```
scheduler.migrate
```

Values

<i>pid</i>	PID of the task being migrated
<i>task</i>	the process that is being migrated
<i>priority</i>	priority of the task being migrated
<i>name</i>	name of the probe point
<i>cpu_to</i>	the destination cpu
<i>cpu_from</i>	the original cpu

probe::scheduler.process_exit

probe::scheduler.process_exit — Process exiting

Synopsis

```
scheduler.process_exit
```

Values

pid PID of the process exiting

name name of the probe point

priority priority of the process exiting

probe::scheduler.process_fork

probe::scheduler.process_fork — Process forked

Synopsis

```
scheduler.process_fork
```

Values

parent_pid PID of the parent process

name name of the probe point

child_pid PID of the child process

probe::scheduler.process_free

probe::scheduler.process_free — Scheduler freeing a data structure for a process

Synopsis

```
scheduler.process_free
```

Values

pid PID of the process getting freed

name name of the probe point

priority priority of the process getting freed

probe::scheduler.process_wait

probe::scheduler.process_wait — Scheduler starting to wait on a process

Synopsis

```
scheduler.process_wait
```

Values

name name of the probe point

pid PID of the process scheduler is waiting on

probe::scheduler.signal_send

probe::scheduler.signal_send — Sending a signal

Synopsis

```
scheduler.signal_send
```

Values

pid pid of the process sending signal

signal_number signal number

name name of the probe point

probe::scheduler.tick

probe::scheduler.tick — Schedulers internal tick, a processes timeslice accounting is updated

Synopsis

```
scheduler.tick
```

Values

idle boolean indicating whether current is the idle process

name name of the probe point

Context

The process whose accounting will be updated.

probe::scheduler.wait_task

probe::scheduler.wait_task — Waiting on a task to unschedule (become inactive)

Synopsis

```
scheduler.wait_task
```

Values

name name of the probe point

task_priority priority of the task

task_pid PID of the task the scheduler is waiting on

probe::scheduler.wakeup

probe::scheduler.wakeup — Task is woken up

Synopsis

`scheduler.wakeup`

Values

<i>name</i>	name of the probe point
<i>task_state</i>	state of the task being woken up
<i>task_priority</i>	priority of the task being woken up
<i>task_pid</i>	PID of the task being woken up
<i>task_tid</i>	tid of the task being woken up
<i>task_cpu</i>	cpu of the task being woken up

probe::scheduler.wakeup_new

probe::scheduler.wakeup_new — Newly created task is woken up for the first time

Synopsis

```
scheduler.wakeup_new
```

Values

<i>task_tid</i>	TID of the new task woken up
<i>task_priority</i>	priority of the new task
<i>task_pid</i>	PID of the new task woken up
<i>task_cpu</i>	cpu of the task woken up
<i>task_state</i>	state of the task woken up
<i>name</i>	name of the probe point

Chapter 9. IO Scheduler and block IO Tapset

This family of probe points is used to probe block IO layer and IO scheduler activities. It contains the following probe points:

probe::ioblock.end

probe::ioblock.end — Fires whenever a block I/O transfer is complete.

Synopsis

`ioblock.end`

Values

None

Description

name - name of the probe point *devname* - block device name *ino* - i-node number of the mapped file *bytes_done* - number of bytes transferred *sector* - beginning sector for the entire bio *flags* - see below BIO_UPTODATE 0 ok after I/O completion BIO_RW_BLOCK 1 RW_AHEAD set, and read/write would block BIO_EOF 2 out-of-bounds error BIO_SEG_VALID 3 nr_hw_seg valid BIO_CLONED 4 doesn't own data BIO_BOUNCED 5 bio is a bounce bio BIO_USER_MAPPED 6 contains user pages BIO_EOPNOTSUPP 7 not supported *error* - 0 on success *rw* - binary trace for read/write request *vcnt* - bio vector count which represents number of array element (page, offset, length) which makes up this I/O request *idx* - offset into the bio vector array *phys_segments* - number of segments in this bio after physical address coalescing is performed. *hw_segments* - number of segments after physical and DMA remapping hardware coalescing is performed *size* - total size in bytes

Context

The process signals the transfer is done.

probe::ioblock.request

probe::ioblock.request — Fires whenever making a generic block I/O request.

Synopsis

```
ioblock.request
```

Values

None

Description

name - name of the probe point *devname* - block device name *ino* - i-node number of the mapped file *sector* - beginning sector for the entire bio *flags* - see below BIO_UPTODATE
0 ok after I/O completion BIO_RW_BLOCK 1 RW_AHEAD set, and read/write would block
BIO_EOF 2 out-out-bounds error BIO_SEG_VALID 3 nr_hw_seg valid BIO_CLONED 4 doesn't own data BIO_BOUNCED 5 bio is a bounce bio BIO_USER_MAPPED 6 contains user pages
BIO_EOPNOTSUPP 7 not supported

rw - binary trace for read/write request *vcnt* - bio vector count which represents number of array element (page, offset, length) which make up this I/O request *idx* - offset into the bio vector array
phys_segments - number of segments in this bio after physical address coalescing is performed
hw_segments - number of segments after physical and DMA remapping hardware coalescing is performed *size* - total size in bytes *bdev* - target block device *bdev_contains* - points to the device object which contains the partition (when bio structure represents a partition) *p_start_sect* - points to the start sector of the partition structure of the device

Context

The process makes block I/O request

probe::ioblock_trace.bounce

probe::ioblock_trace.bounce — Fires whenever a buffer bounce is needed for at least one page of a block IO request.

Synopsis

```
ioblock_trace.bounce
```

Values

None

Description

name - name of the probe point *q* - request queue on which this bio was queued. *devname* - device for which a buffer bounce was needed. *ino* - i-node number of the mapped file *bytes_done* - number of bytes transferred *sector* - beginning sector for the entire bio *flags* - see below BIO_UPTODATE 0 ok after I/O completion BIO_RW_BLOCK 1 RW_AHEAD set, and read/write would block BIO_EOF 2 out-out-bounds error BIO_SEG_VALID 3 nr_hw_seg valid BIO_CLONED 4 doesn't own data BIO_BOUNCED 5 bio is a bounce bio BIO_USER_MAPPED 6 contains user pages BIO_EOPNOTSUPP 7 not supported *rw* - binary trace for read/write request *vcnt* - bio vector count which represents number of array element (page, offset, length) which makes up this I/O request *idx* - offset into the bio vector array *phys_segments* - number of segments in this bio after physical address coalescing is performed. *size* - total size in bytes *bdev* - target block device *bdev_contains* - points to the device object which contains the partition (when bio structure represents a partition) *p_start_sect* - points to the start sector of the partition structure of the device

Context

The process creating a block IO request.

probe::ioblock_trace.end

probe::ioblock_trace.end — Fires whenever a block I/O transfer is complete.

Synopsis

```
ioblock_trace.end
```

Values

None

Description

name - name of the probe point *q* - request queue on which this bio was queued. *devname* - block device name *ino* - i-node number of the mapped file *bytes_done* - number of bytes transferred *sector* - beginning sector for the entire bio *flags* - see below BIO_UPTODATE 0 ok after I/O completion BIO_RW_BLOCK 1 RW_AHEAD set, and read/write would block BIO_EOF 2 out-out-bounds error BIO_SEG_VALID 3 nr_hw_seg valid BIO_CLONED 4 doesn't own data BIO_BOUNCED 5 bio is a bounce bio BIO_USER_MAPPED 6 contains user pages BIO_EOPNOTSUPP 7 not supported

rw - binary trace for read/write request *vcnt* - bio vector count which represents number of array element (page, offset, length) which makes up this I/O request *idx* - offset into the bio vector array *phys_segments* - number of segments in this bio after physical address coalescing is performed. *size* - total size in bytes *bdev* - target block device *bdev_contains* - points to the device object which contains the partition (when bio structure represents a partition) *p_start_sect* - points to the start sector of the partition structure of the device

Context

The process signals the transfer is done.

probe::ioblock_trace.request

probe::ioblock_trace.request — Fires just as a generic block I/O request is created for a bio.

Synopsis

```
ioblock_trace.request
```

Values

None

Description

name - name of the probe point *q* - request queue on which this bio was queued. *devname* - block device name *ino* - i-node number of the mapped file *bytes_done* - number of bytes transferred *sector* - beginning sector for the entire bio *flags* - see below BIO_UPTODATE 0 ok after I/O completion BIO_RW_BLOCK 1 RW_AHEAD set, and read/write would block BIO_EOF 2 out-out-bounds error BIO_SEG_VALID 3 nr_hw_seg valid BIO_CLONED 4 doesn't own data BIO_BOUNCED 5 bio is a bounce bio BIO_USER_MAPPED 6 contains user pages BIO_EOPNOTSUPP 7 not supported

rw - binary trace for read/write request *vcnt* - bio vector count which represents number of array element (page, offset, length) which make up this I/O request *idx* - offset into the bio vector array *phys_segments* - number of segments in this bio after physical address coalescing is performed. *size* - total size in bytes *bdev* - target block device *bdev_contains* - points to the device object which contains the partition (when bio structure represents a partition) *p_start_sect* - points to the start sector of the partition structure of the device

Context

The process makes block I/O request

probe::ioscheduler.elv_add_request

probe::ioscheduler.elv_add_request — probe to indicate request is added to the request queue.

Synopsis

```
ioscheduler.elv_add_request
```

Values

<i>disk_minor</i>	Disk minor number of request.
<i>rq_flags</i>	Request flags.
<i>elevator_name</i>	The type of I/O elevator currently enabled.
<i>disk_major</i>	Disk major no of request.
<i>rq</i>	Address of request.
<i>q</i>	Pointer to request queue.

probe::ioscheduler.elv_add_request.kp

probe::ioscheduler.elv_add_request.kp — kprobe based probe to indicate that a request was added to the request queue

Synopsis

`ioscheduler.elv_add_request.kp`

Values

<i>q</i>	pointer to request queue
<i>rq</i>	Address of the request
<i>elevator_name</i>	The type of I/O elevator currently enabled
<i>disk_major</i>	Disk major number of the request
<i>name</i>	Name of the probe point
<i>rq_flags</i>	Request flags
<i>disk_minor</i>	Disk minor number of the request

probe::ioscheduler.elv_add_request.tp

probe::ioscheduler.elv_add_request.tp — tracepoint based probe to indicate a request is added to the request queue.

Synopsis

```
ioscheduler.elv_add_request.tp
```

Values

<i>q</i>	Pointer to request queue.
<i>rq</i>	Address of request.
<i>elevator_name</i>	The type of I/O elevator currently enabled.
<i>disk_major</i>	Disk major no of request.
<i>name</i>	Name of the probe point
<i>rq_flags</i>	Request flags.
<i>disk_minor</i>	Disk minor number of request.

probe::ioscheduler.elv_completed_request

probe::ioscheduler.elv_completed_request — Fires when a request is completed

Synopsis

`ioscheduler.elv_completed_request`

Values

<i>name</i>	Name of the probe point
<i>rq_flags</i>	Request flags
<i>disk_minor</i>	Disk minor number of the request
<i>elevator_name</i>	The type of I/O elevator currently enabled
<i>disk_major</i>	Disk major number of the request
<i>rq</i>	Address of the request

probe::ioscheduler.elv_next_request

probe::ioscheduler.elv_next_request — Fires when a request is retrieved from the request queue

Synopsis

```
ioscheduler.elv_next_request
```

Values

elevator_name The type of I/O elevator currently enabled

name Name of the probe point

probe::ioscheduler.elv_next_request.return

probe::ioscheduler.elv_next_request.return — Fires when a request retrieval issues a return signal

Synopsis

```
ioscheduler.elv_next_request.return
```

Values

rq Address of the request

disk_major Disk major number of the request

name Name of the probe point

rq_flags Request flags

disk_minor Disk minor number of the request

probe::ioscheduler_trace.elv_abort_request

probe::ioscheduler_trace.elv_abort_request — Fires when a request is aborted.

Synopsis

`ioscheduler_trace.elv_abort_request`

Values

<i>disk_major</i>	Disk major no of request.
<i>elevator_name</i>	The type of I/O elevator currently enabled.
<i>disk_minor</i>	Disk minor number of request.
<i>name</i>	Name of the probe point
<i>rq_flags</i>	Request flags.
<i>rq</i>	Address of request.

probe::ioscheduler_trace.elv_completed_request

probe::ioscheduler_trace.elv_completed_request — Fires when a request is

Synopsis

```
ioscheduler_trace.elv_completed_request
```

Values

<i>name</i>	Name of the probe point
<i>rq_flags</i>	Request flags.
<i>disk_minor</i>	Disk minor number of request.
<i>elevator_name</i>	The type of I/O elevator currently enabled.
<i>disk_major</i>	Disk major no of request.
<i>rq</i>	Address of request.

Description

completed.

probe::ioscheduler_trace.elv_issue_request

probe::ioscheduler_trace.elv_issue_request — Fires when a request is

Synopsis

`ioscheduler_trace.elv_issue_request`

Values

<i>disk_major</i>	Disk major no of request.
<i>elevator_name</i>	The type of I/O elevator currently enabled.
<i>disk_minor</i>	Disk minor number of request.
<i>name</i>	Name of the probe point
<i>rq_flags</i>	Request flags.
<i>rq</i>	Address of request.

Description

scheduled.

probe::ioscheduler_trace.elv_requeue_request

probe::ioscheduler_trace.elv_requeue_request — Fires when a request is

Synopsis

```
ioscheduler_trace.elv_requeue_request
```

Values

<i>name</i>	Name of the probe point
<i>rq_flags</i>	Request flags.
<i>disk_minor</i>	Disk minor number of request.
<i>elevator_name</i>	The type of I/O elevator currently enabled.
<i>disk_major</i>	Disk major no of request.
<i>rq</i>	Address of request.

Description

put back on the queue, when the hardware cannot accept more requests.

probe::ioscheduler_trace.plug

probe::ioscheduler_trace.plug — Fires when a request queue is plugged;

Synopsis

`ioscheduler_trace.plug`

Values

rq_queue request queue

name Name of the probe point

Description

ie, requests in the queue cannot be serviced by block driver.

probe::ioscheduler_trace.unplug_io

probe::ioscheduler_trace.unplug_io — Fires when a request queue is unplugged;

Synopsis

```
ioscheduler_trace.unplug_io
```

Values

name Name of the probe point

rq_queue request queue

Description

Either, when number of pending requests in the queue exceeds threshold or, upon expiration of timer that was activated when queue was plugged.

probe::ioscheduler_trace.unplug_timer

probe::ioscheduler_trace.unplug_timer — Fires when unplug timer associated

Synopsis

```
ioscheduler_trace.unplug_timer
```

Values

name Name of the probe point

rq_queue request queue

Description

with a request queue expires.

Chapter 10. SCSI Tapset

This family of probe points is used to probe SCSI activities. It contains the following probe points:

probe::scsi.iocompleted

probe::scsi.iocompleted — SCSI mid-layer running the completion processing for block device I/O requests

Synopsis

```
scsi.iocompleted
```

Values

<i>channel</i>	The channel number
<i>device_state_str</i>	The current state of the device, as a string
<i>dev_id</i>	The scsi device id
<i>req_addr</i>	The current struct request pointer, as a number
<i>data_direction_str</i>	Data direction, as a string
<i>data_direction</i>	The data_direction specifies whether this command is from/to the device
<i>lun</i>	The lun number
<i>goodbytes</i>	The bytes completed
<i>host_no</i>	The host number
<i>device_state</i>	The current state of the device

probe::scsi.iodispatching

probe::scsi.iodispatching — SCSI mid-layer dispatched low-level SCSI command

Synopsis

```
scsi.iodispatching
```

Values

<i>req_addr</i>	The current struct request pointer, as a number
<i>data_direction_str</i>	Data direction, as a string
<i>dev_id</i>	The scsi device id
<i>data_direction</i>	The <i>data_direction</i> specifies whether this command is from/to the device 0 (DMA_BIDIRECTIONAL), 1 (DMA_TO_DEVICE), 2 (DMA_FROM_DEVICE), 3 (DMA_NONE)
<i>channel</i>	The channel number
<i>device_state_str</i>	The current state of the device, as a string
<i>host_no</i>	The host number
<i>request_buffer</i>	The request buffer address
<i>device_state</i>	The current state of the device
<i>request_bufflen</i>	The request buffer length
<i>lun</i>	The lun number

probe::scsi.iodone

probe::scsi.iodone — SCSI command completed by low level driver and enqueued into the done queue.

Synopsis

```
scsi.iodone
```

Values

<i>lun</i>	The lun number
<i>host_no</i>	The host number
<i>device_state</i>	The current state of the device
<i>channel</i>	The channel number
<i>device_state_str</i>	The current state of the device, as a string
<i>scsi_timer_pending</i>	1 if a timer is pending on this request
<i>dev_id</i>	The scsi device id
<i>req_addr</i>	The current struct request pointer, as a number
<i>data_direction_str</i>	Data direction, as a string
<i>data_direction</i>	The data_direction specifies whether this command is from/to the device.

probe::scsi.ioentry

probe::scsi.ioentry — Prepares a SCSI mid-layer request

Synopsis

```
scsi.ioentry
```

Values

<i>req_addr</i>	The current struct request pointer, as a number
<i>device_state</i>	The current state of the device
<i>device_state_str</i>	The current state of the device, as a string
<i>disk_minor</i>	The minor number of the disk (-1 if no information)
<i>disk_major</i>	The major number of the disk (-1 if no information)

probe::scsi.ioexecute

probe::scsi.ioexecute — Create mid-layer SCSI request and wait for the result

Synopsis

```
scsi.ioexecute
```

Values

<i>retries</i>	Number of times to retry request
<i>dev_id</i>	The scsi device id
<i>data_direction_str</i>	Data direction, as a string
<i>data_direction</i>	The data_direction specifies whether this command is from/to the device.
<i>channel</i>	The channel number
<i>device_state_str</i>	The current state of the device, as a string
<i>host_no</i>	The host number
<i>request_buffer</i>	The data buffer address
<i>device_state</i>	The current state of the device
<i>request_bufflen</i>	The data buffer buffer length
<i>timeout</i>	Request timeout in seconds
<i>lun</i>	The lun number

probe::scsi.set_state

probe::scsi.set_state — Order SCSI device state change

Synopsis

```
scsi.set_state
```

Values

<i>state</i>	The new state of the device
<i>lun</i>	The lun number
<i>old_state_str</i>	The current state of the device, as a string
<i>host_no</i>	The host number
<i>channel</i>	The channel number
<i>dev_id</i>	The scsi device id
<i>state_str</i>	The new state of the device, as a string
<i>old_state</i>	The current state of the device

Chapter 11. TTY Tapset

This family of probe points is used to probe TTY (Teletype) activities. It contains the following probe points:

probe::tty.init

probe::tty.init — Called when a tty is being initialized

Synopsis

`tty.init`

Values

driver_name the driver name

name the driver .dev_name name

module the module name

probe::tty.ioctl

probe::tty.ioctl — called when a ioctl is request to the tty

Synopsis

`tty.ioctl`

Values

name the file name

cmd the ioctl command

arg the ioctl argument

probe::tty.open

probe::tty.open — Called when a tty is opened

Synopsis

`tty.open`

Values

<i>file_flags</i>	the file flags
<i>inode_flags</i>	the inode flags
<i>inode_state</i>	the inode state
<i>file_mode</i>	the file mode
<i>file_name</i>	the file name
<i>inode_number</i>	the inode number

probe::tty.poll

probe::tty.poll — Called when a tty device is being polled

Synopsis

`tty.poll`

Values

file_name the tty file name

wait_key the wait queue key

probe::tty.read

probe::tty.read — called when a tty line will be read

Synopsis

`tty.read`

Values

file_name the file name lreated to the tty

driver_name the driver name

buffer the buffer that will receive the characters

nr The amount of characters to be read

probe::tty.receive

probe::tty.receive — called when a tty receives a message

Synopsis

```
tty.receive
```

Values

<i>cp</i>	the buffer that was received
<i>driver_name</i>	the driver name
<i>index</i>	The tty Index
<i>fp</i>	The flag buffer
<i>count</i>	The amount of characters received
<i>id</i>	the tty id
<i>name</i>	the name of the module file

probe::tty.register

probe::tty.register — Called when a tty device is registered

Synopsis

```
tty.register
```

Values

index the tty index requested

driver_name the driver name

module the module name

name the driver .dev_name name

probe::tty.release

probe::tty.release — Called when the tty is closed

Synopsis

`tty.release`

Values

<i>file_flags</i>	the file flags
<i>inode_flags</i>	the inode flags
<i>inode_state</i>	the inode state
<i>file_name</i>	the file name
<i>file_mode</i>	the file mode
<i>inode_number</i>	the inode number

probe::tty.resize

probe::tty.resize — Called when a terminal resize happens

Synopsis

`tty.resize`

Values

new_ypixel the new ypixel value

old_row the old row value

new_xpixel the new xpixel value

new_col the new col value

old_xpixel the old xpixel

old_ypixel the old ypixel

old_col the old col value

name the tty name

new_row the new row value

probe::tty.unregister

probe::tty.unregister — Called when a tty device is being unregistered

Synopsis

```
tty.unregister
```

Values

index the tty index requested

driver_name the driver name

module the module name

name the driver .dev_name name

probe::tty.write

probe::tty.write — write to the tty line

Synopsis

```
tty.write
```

Values

<i>nr</i>	The amount of characters
<i>buffer</i>	the buffer that will be written
<i>driver_name</i>	the driver name
<i>file_name</i>	the file name lreated to the tty

Chapter 12. Interrupt Request (IRQ) Tapset

This family of probe points is used to probe interrupt request (IRQ) activities. It contains the following probe points:

probe::irq_handler.entry

probe::irq_handler.entry — Execution of interrupt handler starting

Synopsis

`irq_handler.entry`

Values

<i>flags_str</i>	symbolic string representation of IRQ flags
<i>dev_name</i>	name of device
<i>next_irqaction</i>	pointer to next irqaction for shared interrupts
<i>thread_flags</i>	Flags related to thread
<i>flags</i>	Flags for IRQ handler
<i>action</i>	struct irqaction* for this interrupt num
<i>dir</i>	pointer to the proc/irq/NN/name entry
<i>thread</i>	thread pointer for threaded interrupts
<i>handler</i>	interrupt handler function
<i>dev_id</i>	Cookie to identify device
<i>thread_fn</i>	interrupt handler function for threaded interrupts
<i>irq</i>	irq number

probe::irq_handler.exit

probe::irq_handler.exit — Execution of interrupt handler completed

Synopsis

```
irq_handler.exit
```

Values

<i>dev_name</i>	name of device
<i>ret</i>	return value of the handler
<i>flags_str</i>	symbolic string representation of IRQ flags
<i>thread_flags</i>	Flags related to thread
<i>next_irqaction</i>	pointer to next irqaction for shared interrupts
<i>dir</i>	pointer to the proc/irq/NN/name entry
<i>action</i>	struct irqaction*
<i>flags</i>	flags for IRQ handler
<i>irq</i>	interrupt number
<i>thread_fn</i>	interrupt handler function for threaded interrupts
<i>dev_id</i>	Cookie to identify device
<i>handler</i>	interrupt handler function that was executed
<i>thread</i>	thread pointer for threaded interrupts

probe::softirq.entry

probe::softirq.entry — Execution of handler for a pending softirq starting

Synopsis

```
softirq.entry
```

Values

<i>vec_nr</i>	softirq vector number
<i>vec</i>	softirq_action vector
<i>action</i>	pointer to softirq handler just about to execute
<i>h</i>	struct softirq_action* for current pending softirq

probe::softirq.exit

probe::softirq.exit — Execution of handler for a pending softirq completed

Synopsis

```
softirq.exit
```

Values

<i>vec</i>	softirq_action vector
<i>h</i>	struct softirq_action* for just executed softirq
<i>action</i>	pointer to softirq handler that just finished execution
<i>vec_nr</i>	softirq vector number

probe::workqueue.create

probe::workqueue.create — Creating a new workqueue

Synopsis

```
workqueue.create
```

Values

wq_thread task_struct of the workqueue thread

cpu cpu for which the worker thread is created

probe::workqueue.destroy

probe::workqueue.destroy — Destroying workqueue

Synopsis

```
workqueue.destroy
```

Values

wq_thread task_struct of the workqueue thread

probe::workqueue.execute

probe::workqueue.execute — Executing deferred work

Synopsis

```
workqueue.execute
```

Values

work work_struct* being executed

work_func pointer to handler function

wq_thread task_struct of the workqueue thread

probe::workqueue.insert

probe::workqueue.insert — Queuing work on a workqueue

Synopsis

```
workqueue.insert
```

Values

work work_struct* being queued

work_func pointer to handler function

wq_thread task_struct of the workqueue thread

Chapter 13. Networking Tapset

This family of probe points is used to probe the activities of the network device and protocol layers.

function::format_ipaddr

function::format_ipaddr — Returns a string representation for an IP address

Synopsis

```
format_ipaddr:string(addr:long,family:long)
```

Arguments

addr the IP address

family the IP address family (either AF_INET or AF_INET6)

function::htonl

function::htonl — Convert 32-bit long from host to network order

Synopsis

```
htonl:long(x:long)
```

Arguments

x Value to convert

function::htonll

function::htonll — Convert 64-bit long long from host to network order

Synopsis

```
htonll:long(x:long)
```

Arguments

x Value to convert

function::htons

function::htons — Convert 16-bit short from host to network order

Synopsis

```
htons:long(x:long)
```

Arguments

x Value to convert

function::ip_ntop

function::ip_ntop — Returns a string representation for an IPv4 address

Synopsis

```
ip_ntop:string(addr:long)
```

Arguments

addr the IPv4 address represented as an integer

function::ntohl

function::ntohl — Convert 32-bit long from network to host order

Synopsis

```
ntohl:long(x:long)
```

Arguments

x Value to convert

function::ntohll

function::ntohll — Convert 64-bit long long from network to host order

Synopsis

```
ntohll:long(x:long)
```

Arguments

x Value to convert

function::ntohs

function::ntohs — Convert 16-bit short from network to host order

Synopsis

```
ntohs:long(x:long)
```

Arguments

x Value to convert

probe::netdev.change_mac

probe::netdev.change_mac — Called when the netdev_name has the MAC changed

Synopsis

`netdev.change_mac`

Values

dev_name The device that will have the MAC changed

new_mac The new MAC address

old_mac The current MAC address

mac_len The MAC length

probe::netdev.change_mtu

probe::netdev.change_mtu — Called when the netdev MTU is changed

Synopsis

`netdev.change_mtu`

Values

new_mtu The new MTU

dev_name The device that will have the MTU changed

old_mtu The current MTU

probe::netdev.change_rx_flag

probe::netdev.change_rx_flag — Called when the device RX flag will be changed

Synopsis

`netdev.change_rx_flag`

Values

dev_name The device that will be changed

flags The new flags

probe::netdev.close

`probe::netdev.close` — Called when the device is closed

Synopsis

`netdev.close`

Values

dev_name The device that is going to be closed

probe::netdev.get_stats

`probe::netdev.get_stats` — Called when someone asks the device statistics

Synopsis

```
netdev.get_stats
```

Values

dev_name The device that is going to provide the statistics

probe::netdev.hard_transmit

probe::netdev.hard_transmit — Called when the devices is going to TX (hard)

Synopsis

```
netdev.hard_transmit
```

Values

length The length of the transmit buffer.

truesize The size of the data to be transmitted.

protocol The protocol used in the transmission

dev_name The device scheduled to transmit

probe::netdev.ioctl

probe::netdev.ioctl — Called when the device suffers an IOCTL

Synopsis

`netdev.ioctl`

Values

arg The IOCTL argument (usually the netdev interface)

cmd The IOCTL request

probe::netdev.open

probe::netdev.open — Called when the device is opened

Synopsis

`netdev.open`

Values

dev_name The device that is going to be opened

probe::netdev.receive

probe::netdev.receive — Data received from network device.

Synopsis

`netdev.receive`

Values

protocol Protocol of received packet.

dev_name The name of the device. e.g: eth0, ath1.

length The length of the receiving buffer.

probe::netdev.register

probe::netdev.register — Called when the device is registered

Synopsis

```
netdev.register
```

Values

dev_name The device that is going to be registered

probe::netdev.rx

probe::netdev.rx — Called when the device is going to receive a packet

Synopsis

`netdev.rx`

Values

dev_name The device received the packet

protocol The packet protocol

probe::netdev.set_promiscuity

probe::netdev.set_promiscuity — Called when the device enters/leaves promiscuity

Synopsis

```
netdev.set_promiscuity
```

Values

dev_name The device that is entering/leaving promiscuity mode

disable If the device is leaving promiscuity mode

enable If the device is entering promiscuity mode

inc Count the number of promiscuity openers

probe::netdev.transmit

probe::netdev.transmit — Network device transmitting buffer

Synopsis

`netdev.transmit`

Values

truesize The size of the data to be transmitted.

length The length of the transmit buffer.

protocol The protocol of this packet(defined in include/linux/if_ether.h).

dev_name The name of the device. e.g: eth0, ath1.

probe::netdev.unregister

probe::netdev.unregister — Called when the device is being unregistered

Synopsis

`netdev.unregister`

Values

dev_name The device that is going to be unregistered

probe::netfilter.arp.forward

probe::netfilter.arp.forward — - Called for each ARP packet to be forwarded

Synopsis

`netfilter.arp.forward`

Values

<code>ar_sha</code>	Ethernet+IP only (ar_pro==0x800): source hardware (MAC) address
<code>ar_tip</code>	Ethernet+IP only (ar_pro==0x800): target IP address
<code>ar_hln</code>	Length of hardware address
<code>nf_queue</code>	Constant used to signify a 'queue' verdict
<code>length</code>	The length of the packet buffer contents, in bytes
<code>ar_data</code>	Address of ARP packet data region (after the header)
<code>pf</code>	Protocol family -- always "arp"
<code>outdev</code>	Address of net_device representing output device, 0 if unknown
<code>ar_pln</code>	Length of protocol address
<code>indev_name</code>	Name of network device packet was received on (if known)
<code>nf_stolen</code>	Constant used to signify a 'stolen' verdict
<code>ar_op</code>	ARP opcode (command)
<code>nf_accept</code>	Constant used to signify an 'accept' verdict
<code>outdev_name</code>	Name of network device packet will be routed to (if known)
<code>nf_drop</code>	Constant used to signify a 'drop' verdict
<code>ar_pro</code>	Format of protocol address
<code>arphdr</code>	Address of ARP header
<code>nf_stop</code>	Constant used to signify a 'stop' verdict
<code>indev</code>	Address of net_device representing input device, 0 if unknown
<code>ar_tha</code>	Ethernet+IP only (ar_pro==0x800): target hardware (MAC) address
<code>ar_hrd</code>	Format of hardware address
<code>ar_sip</code>	Ethernet+IP only (ar_pro==0x800): source IP address
<code>nf_repeat</code>	Constant used to signify a 'repeat' verdict

probe::netfilter.arp.in

probe::netfilter.arp.in — - Called for each incoming ARP packet

Synopsis

`netfilter.arp.in`

Values

<i>pf</i>	Protocol family -- always "arp"
<i>ar_data</i>	Address of ARP packet data region (after the header)
<i>length</i>	The length of the packet buffer contents, in bytes
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>ar_hln</i>	Length of hardware address
<i>ar_tip</i>	Ethernet+IP only (ar_pro==0x800): target IP address
<i>ar_sha</i>	Ethernet+IP only (ar_pro==0x800): source hardware (MAC) address
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>ar_op</i>	ARP opcode (command)
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>ar_pln</i>	Length of protocol address
<i>outdev</i>	Address of net_device representing output device, 0 if unknown
<i>ar_tha</i>	Ethernet+IP only (ar_pro==0x800): target hardware (MAC) address
<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>arphdr</i>	Address of ARP header
<i>ar_pro</i>	Format of protocol address
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>ar_sip</i>	Ethernet+IP only (ar_pro==0x800): source IP address
<i>ar_hrd</i>	Format of hardware address

probe::netfilter.arp.out

probe::netfilter.arp.out — - Called for each outgoing ARP packet

Synopsis

`netfilter.arp.out`

Values

<code>ar_data</code>	Address of ARP packet data region (after the header)
<code>pf</code>	Protocol family -- always "arp"
<code>length</code>	The length of the packet buffer contents, in bytes
<code>ar_sha</code>	Ethernet+IP only (ar_pro==0x800): source hardware (MAC) address
<code>ar_tip</code>	Ethernet+IP only (ar_pro==0x800): target IP address
<code>ar_hln</code>	Length of hardware address
<code>nf_queue</code>	Constant used to signify a 'queue' verdict
<code>ar_op</code>	ARP opcode (command)
<code>nf_stolen</code>	Constant used to signify a 'stolen' verdict
<code>nf_accept</code>	Constant used to signify an 'accept' verdict
<code>outdev_name</code>	Name of network device packet will be routed to (if known)
<code>outdev</code>	Address of net_device representing output device, 0 if unknown
<code>ar_pln</code>	Length of protocol address
<code>indev_name</code>	Name of network device packet was received on (if known)
<code>ar_tha</code>	Ethernet+IP only (ar_pro==0x800): target hardware (MAC) address
<code>nf_stop</code>	Constant used to signify a 'stop' verdict
<code>indev</code>	Address of net_device representing input device, 0 if unknown
<code>arphdr</code>	Address of ARP header
<code>ar_pro</code>	Format of protocol address
<code>nf_drop</code>	Constant used to signify a 'drop' verdict
<code>nf_repeat</code>	Constant used to signify a 'repeat' verdict
<code>ar_sip</code>	Ethernet+IP only (ar_pro==0x800): source IP address
<code>ar_hrd</code>	Format of hardware address

probe::netfilter.bridge.forward

probe::netfilter.bridge.forward — Called on an incoming bridging packet destined for some other computer

Synopsis

`netfilter.bridge.forward`

Values

<i>pf</i>	Protocol family -- always "bridge"
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>length</i>	The length of the packet buffer contents, in bytes
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>outdev</i>	Address of net_device representing output device, 0 if unknown
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict

probe::netfilter.bridge.local_in

probe::netfilter.bridge.local_in — Called on a bridging packet destined for the local computer

Synopsis

`netfilter.bridge.local_in`

Values

<code>nf_queue</code>	Constant used to signify a 'queue' verdict
<code>length</code>	The length of the packet buffer contents, in bytes
<code>pf</code>	Protocol family -- always "bridge"
<code>indev_name</code>	Name of network device packet was received on (if known)
<code>outdev</code>	Address of net_device representing output device, 0 if unknown
<code>nf_accept</code>	Constant used to signify an 'accept' verdict
<code>outdev_name</code>	Name of network device packet will be routed to (if known)
<code>nf_stolen</code>	Constant used to signify a 'stolen' verdict
<code>nf_drop</code>	Constant used to signify a 'drop' verdict
<code>nf_stop</code>	Constant used to signify a 'stop' verdict
<code>indev</code>	Address of net_device representing input device, 0 if unknown
<code>nf_repeat</code>	Constant used to signify a 'repeat' verdict

probe::netfilter.bridge.local_out

probe::netfilter.bridge.local_out — Called on a bridging packet coming from a local process

Synopsis

`netfilter.bridge.local_out`

Values

<i>length</i>	The length of the packet buffer contents, in bytes
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>pf</i>	Protocol family -- always "bridge"
<i>outdev</i>	Address of net_device representing output device, 0 if unknown
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict

probe::netfilter.bridge.post_routing

probe::netfilter.bridge.post_routing — - Called before a bridging packet hits the wire

Synopsis

`netfilter.bridge.post_routing`

Values

<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>pf</i>	Protocol family -- always "bridge"
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>length</i>	The length of the packet buffer contents, in bytes
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>outdev</i>	Address of net_device representing output device, 0 if unknown

probe::netfilter.bridge.pre_routing

probe::netfilter.bridge.pre_routing — - Called before a bridging packet is routed

Synopsis

`netfilter.bridge.pre_routing`

Values

<i>outdev</i>	Address of net_device representing output device, 0 if unknown
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>length</i>	The length of the packet buffer contents, in bytes
<i>pf</i>	Protocol family -- always “bridge”
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>indev</i>	Address of net_device representing input device, 0 if unknown

probe::netfilter.ip.forward

probe::netfilter.ip.forward — Called on an incoming IP packet addressed to some other computer

Synopsis

`netfilter.ip.forward`

Values

<i>protocol</i>	Packet protocol from driver (ipv4 only)
<i>pf</i>	Protocol family -- either "ipv4" or "ipv6"
<i>psh</i>	TCP PSH flag (if protocol is TCP; ipv4 only)
<i>length</i>	The length of the packet buffer contents, in bytes
<i>fin</i>	TCP FIN flag (if protocol is TCP; ipv4 only)
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>sport</i>	TCP or UDP source port (ipv4 only)
<i>ipproto_udp</i>	Constant used to signify that the packet protocol is UDP
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>syn</i>	TCP SYN flag (if protocol is TCP; ipv4 only)
<i>urg</i>	TCP URG flag (if protocol is TCP; ipv4 only)
<i>saddr</i>	A string representing the source IP address
<i>daddr</i>	A string representing the destination IP address
<i>outdev</i>	Address of net_device representing output device, 0 if unknown
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>iphdr</i>	Address of IP header
<i>dport</i>	TCP or UDP destination port (ipv4 only)
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>ack</i>	TCP ACK flag (if protocol is TCP; ipv4 only)
<i>ipproto_tcp</i>	Constant used to signify that the packet protocol is TCP
<i>rst</i>	TCP RST flag (if protocol is TCP; ipv4 only)

family IP address family

probe::netfilter.ip.local_in

probe::netfilter.ip.local_in — Called on an incoming IP packet addressed to the local computer

Synopsis

`netfilter.ip.local_in`

Values

<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>ipproto_udp</i>	Constant used to signify that the packet protocol is UDP
<i>outdev</i>	Address of net_device representing output device, 0 if unknown
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>syn</i>	TCP SYN flag (if protocol is TCP; ipv4 only)
<i>daddr</i>	A string representing the destination IP address
<i>urg</i>	TCP URG flag (if protocol is TCP; ipv4 only)
<i>saddr</i>	A string representing the source IP address
<i>protocol</i>	Packet protocol from driver (ipv4 only)
<i>pf</i>	Protocol family -- either "ipv4" or "ipv6"
<i>fin</i>	TCP FIN flag (if protocol is TCP; ipv4 only)
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>sport</i>	TCP or UDP source port (ipv4 only)
<i>length</i>	The length of the packet buffer contents, in bytes
<i>psh</i>	TCP PSH flag (if protocol is TCP; ipv4 only)
<i>ipproto_tcp</i>	Constant used to signify that the packet protocol is TCP
<i>ack</i>	TCP ACK flag (if protocol is TCP; ipv4 only)
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>family</i>	IP address family
<i>rst</i>	TCP RST flag (if protocol is TCP; ipv4 only)
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>iphdr</i>	Address of IP header
<i>nf_drop</i>	Constant used to signify a 'drop' verdict

dport TCP or UDP destination port (ipv4 only)

probe::netfilter.ip.local_out

probe::netfilter.ip.local_out — Called on an outgoing IP packet

Synopsis

`netfilter.ip.local_out`

Values

<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>dport</i>	TCP or UDP destination port (ipv4 only)
<i>iphdr</i>	Address of IP header
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>ack</i>	TCP ACK flag (if protocol is TCP; ipv4 only)
<i>ipproto_tcp</i>	Constant used to signify that the packet protocol is TCP
<i>rst</i>	TCP RST flag (if protocol is TCP; ipv4 only)
<i>family</i>	IP address family
<i>pf</i>	Protocol family -- either "ipv4" or "ipv6"
<i>protocol</i>	Packet protocol from driver (ipv4 only)
<i>length</i>	The length of the packet buffer contents, in bytes
<i>psh</i>	TCP PSH flag (if protocol is TCP; ipv4 only)
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>sport</i>	TCP or UDP source port (ipv4 only)
<i>fin</i>	TCP FIN flag (if protocol is TCP; ipv4 only)
<i>ipproto_udp</i>	Constant used to signify that the packet protocol is UDP
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>daddr</i>	A string representing the destination IP address
<i>urg</i>	TCP URG flag (if protocol is TCP; ipv4 only)
<i>saddr</i>	A string representing the source IP address
<i>syn</i>	TCP SYN flag (if protocol is TCP; ipv4 only)
<i>indev_name</i>	Name of network device packet was received on (if known)

outdev Address of net_device representing output device, 0 if unknown

probe::netfilter.ip.post_routing

probe::netfilter.ip.post_routing — Called immediately before an outgoing IP packet leaves the computer

Synopsis

`netfilter.ip.post_routing`

Values

<i>dport</i>	TCP or UDP destination port (ipv4 only)
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>iphdr</i>	Address of IP header
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>family</i>	IP address family
<i>rst</i>	TCP RST flag (if protocol is TCP; ipv4 only)
<i>ack</i>	TCP ACK flag (if protocol is TCP; ipv4 only)
<i>ipproto_tcp</i>	Constant used to signify that the packet protocol is TCP
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>sport</i>	TCP or UDP source port (ipv4 only)
<i>fin</i>	TCP FIN flag (if protocol is TCP; ipv4 only)
<i>length</i>	The length of the packet buffer contents, in bytes
<i>psh</i>	TCP PSH flag (if protocol is TCP; ipv4 only)
<i>pf</i>	Protocol family -- either "ipv4" or "ipv6"
<i>protocol</i>	Packet protocol from driver (ipv4 only)
<i>indev_name</i>	Name of network device packet was received on (if known)
<i>outdev</i>	Address of net_device representing output device, 0 if unknown
<i>saddr</i>	A string representing the source IP address
<i>urg</i>	TCP URG flag (if protocol is TCP; ipv4 only)
<i>daddr</i>	A string representing the destination IP address
<i>syn</i>	TCP SYN flag (if protocol is TCP; ipv4 only)
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_accept</i>	Constant used to signify an 'accept' verdict

nf_stolen Constant used to signify a 'stolen' verdict

ipproto_udp Constant used to signify that the packet protocol is UDP

probe::netfilter.ip.pre_routing

probe::netfilter.ip.pre_routing — Called before an IP packet is routed

Synopsis

```
netfilter.ip.pre_routing
```

Values

<i>nf_stop</i>	Constant used to signify a 'stop' verdict
<i>indev</i>	Address of net_device representing input device, 0 if unknown
<i>dport</i>	TCP or UDP destination port (ipv4 only)
<i>nf_drop</i>	Constant used to signify a 'drop' verdict
<i>iphdr</i>	Address of IP header
<i>nf_repeat</i>	Constant used to signify a 'repeat' verdict
<i>ipproto_tcp</i>	Constant used to signify that the packet protocol is TCP
<i>ack</i>	TCP ACK flag (if protocol is TCP; ipv4 only)
<i>family</i>	IP address family
<i>rst</i>	TCP RST flag (if protocol is TCP; ipv4 only)
<i>pf</i>	Protocol family - either 'ipv4' or 'ipv6'
<i>protocol</i>	Packet protocol from driver (ipv4 only)
<i>length</i>	The length of the packet buffer contents, in bytes
<i>psh</i>	TCP PSH flag (if protocol is TCP; ipv4 only)
<i>sport</i>	TCP or UDP source port (ipv4 only)
<i>nf_queue</i>	Constant used to signify a 'queue' verdict
<i>fin</i>	TCP FIN flag (if protocol is TCP; ipv4 only)
<i>ipproto_udp</i>	Constant used to signify that the packet protocol is UDP
<i>nf_accept</i>	Constant used to signify an 'accept' verdict
<i>outdev_name</i>	Name of network device packet will be routed to (if known)
<i>nf_stolen</i>	Constant used to signify a 'stolen' verdict
<i>saddr</i>	A string representing the source IP address
<i>urg</i>	TCP URG flag (if protocol is TCP; ipv4 only)
<i>daddr</i>	A string representing the destination IP address
<i>syn</i>	TCP SYN flag (if protocol is TCP; ipv4 only)
<i>indev_name</i>	Name of network device packet was received on (if known)

outdev Address of net_device representing output device, 0 if unknown

probe::sunrpc.clnt.bind_new_program

probe::sunrpc.clnt.bind_new_program — Bind a new RPC program to an existing client

Synopsis

```
sunrpc.clnt.bind_new_program
```

Values

<i>old_progname</i>	the name of old RPC program
<i>progname</i>	the name of new RPC program
<i>vers</i>	the version of new RPC program
<i>servername</i>	the server machine name
<i>prog</i>	the number of new RPC program
<i>old_vers</i>	the version of old RPC program
<i>old_prog</i>	the number of old RPC program

probe::sunrpc.clnt.call_async

probe::sunrpc.clnt.call_async — Make an asynchronous RPC call

Synopsis

```
sunrpc.clnt.call_async
```

Values

<i>flags</i>	flags
<i>proc</i>	the procedure number in this RPC call
<i>dead</i>	whether this client is abandoned
<i>prog</i>	the RPC program number
<i>port</i>	the port number
<i>progname</i>	the RPC program name
<i>servername</i>	the server machine name
<i>vers</i>	the RPC program version number
<i>procname</i>	the procedure name in this RPC call
<i>xid</i>	current transmission id
<i>prot</i>	the IP protocol number

probe::sunrpc.clnt.call_sync

probe::sunrpc.clnt.call_sync — Make a synchronous RPC call

Synopsis

```
sunrpc.clnt.call_sync
```

Values

<i>prot</i>	the IP protocol number
<i>xid</i>	current transmission id
<i>procname</i>	the procedure name in this RPC call
<i>servername</i>	the server machine name
<i>vers</i>	the RPC program version number
<i>progname</i>	the RPC program name
<i>port</i>	the port number
<i>prog</i>	the RPC program number
<i>dead</i>	whether this client is abandoned
<i>proc</i>	the procedure number in this RPC call
<i>flags</i>	flags

probe::sunrpc.clnt.clone_client

probe::sunrpc.clnt.clone_client — Clone an RPC client structure

Synopsis

```
sunrpc.clnt.clone_client
```

Values

<i>port</i>	the port number
<i>authflavor</i>	the authentication flavor
<i>prog</i>	the RPC program number
<i>prot</i>	the IP protocol number
<i>servername</i>	the server machine name
<i>vers</i>	the RPC program version number
<i>progname</i>	the RPC program name

probe::sunrpc.clnt.create_client

probe::sunrpc.clnt.create_client — Create an RPC client

Synopsis

```
sunrpc.clnt.create_client
```

Values

<i>progname</i>	the RPC program name
<i>servername</i>	the server machine name
<i>prot</i>	the IP protocol number
<i>vers</i>	the RPC program version number
<i>authflavor</i>	the authentication flavor
<i>prog</i>	the RPC program number
<i>port</i>	the port number

probe::sunrpc.clnt.restart_call

probe::sunrpc.clnt.restart_call — Restart an asynchronous RPC call

Synopsis

```
sunrpc.clnt.restart_call
```

Values

<i>xid</i>	the transmission id
<i>servername</i>	the server machine name
<i>prog</i>	the RPC program number
<i>tk_priority</i>	the task priority
<i>tk_runstate</i>	the task run status
<i>tk_pid</i>	the debugging aid of task
<i>tk_flags</i>	the task flags

probe::sunrpc.clnt.shutdown_client

probe::sunrpc.clnt.shutdown_client — Shutdown an RPC client

Synopsis

```
sunrpc.clnt.shutdown_client
```

Values

<i>om_ntrans</i>	the count of RPC transmissions
<i>om_ops</i>	the count of operations
<i>om_rtt</i>	the RPC RTT jiffies
<i>om_queue</i>	the jiffies queued for xmit
<i>rpccnt</i>	the count of RPC calls
<i>om_bytes_recv</i>	the count of bytes in
<i>tasks</i>	the number of references
<i>prot</i>	the IP protocol number
<i>prog</i>	the RPC program number
<i>authflavor</i>	the authentication flavor
<i>port</i>	the port number
<i>clones</i>	the number of clones
<i>om_execute</i>	the RPC execution jiffies
<i>om_bytes_sent</i>	the count of bytes out
<i>progname</i>	the RPC program name
<i>netreconn</i>	the count of reconnections
<i>servername</i>	the server machine name
<i>vers</i>	the RPC program version number

probe::sunrpc.sched.delay

probe::sunrpc.sched.delay — Delay an RPC task

Synopsis

`sunrpc.sched.delay`

Values

<i>prog</i>	the program number in the RPC call
<i>vers</i>	the program version in the RPC call
<i>prot</i>	the IP protocol in the RPC call
<i>xid</i>	the transmission id in the RPC call
<i>delay</i>	the time delayed
<i>tk_flags</i>	the flags of the task
<i>tk_pid</i>	the debugging id of the task

probe::sunrpc.sched.execute

probe::sunrpc.sched.execute — Execute the RPC `scheduler'

Synopsis

```
sunrpc.sched.execute
```

Values

<i>xid</i>	the transmission id in the RPC call
<i>prot</i>	the IP protocol in the RPC call
<i>prog</i>	the program number in the RPC call
<i>vers</i>	the program version in the RPC call
<i>tk_flags</i>	the flags of the task
<i>tk_pid</i>	the debugging id of the task

probe::sunrpc.sched.new_task

probe::sunrpc.sched.new_task — Create new task for the specified client

Synopsis

```
sunrpc.sched.new_task
```

Values

<i>vers</i>	the program version in the RPC call
<i>prog</i>	the program number in the RPC call
<i>xid</i>	the transmission id in the RPC call
<i>prot</i>	the IP protocol in the RPC call
<i>tk_flags</i>	the flags of the task

probe::sunrpc.sched.release_task

probe::sunrpc.sched.release_task — Release all resources associated with a task

Synopsis

```
sunrpc.sched.release_task
```

Values

<i>xid</i>	the transmission id in the RPC call
<i>prot</i>	the IP protocol in the RPC call
<i>vers</i>	the program version in the RPC call
<i>prog</i>	the program number in the RPC call
<i>tk_flags</i>	the flags of the task

Description

rpc_release_task function might not be found for a particular kernel. So, if we can't find it, just return '-1' for everything.

probe::sunrpc.svc.create

probe::sunrpc.svc.create — Create an RPC service

Synopsis

```
sunrpc.svc.create
```

Values

pg_nvers the number of supported versions

progname the name of the program

prog the number of the program

bufsize the buffer size

probe::sunrpc.svc.destroy

probe::sunrpc.svc.destroy — Destroy an RPC service

Synopsis

```
sunrpc.svc.destroy
```

Values

<i>sv_name</i>	the service name
<i>sv_prog</i>	the number of the program
<i>rpcbadauth</i>	the count of requests dropped for authentication failure
<i>rpccnt</i>	the count of valid RPC requests
<i>nettcpconn</i>	the count of accepted TCP connections
<i>sv_progname</i>	the name of the program
<i>rpcbadfmt</i>	the count of requests dropped for bad formats
<i>netcnt</i>	the count of received RPC requests
<i>sv_nrthreads</i>	the number of concurrent threads

probe::sunrpc.svc.drop

probe::sunrpc.svc.drop — Drop RPC request

Synopsis

`sunrpc.svc.drop`

Values

rq_vers the program version in the request

rq_prog the program number in the request

sv_name the service name

rq_proc the procedure number in the request

peer_ip the peer address where the request is from

rq_xid the transmission id in the request

rq_prot the IP protocol of the request

probe::sunrpc.svc.process

probe::sunrpc.svc.process — Process an RPC request

Synopsis

`sunrpc.svc.process`

Values

<i>rq_xid</i>	the transmission id in the request
<i>sv_nrthreads</i>	the number of concurrent threads
<i>rq_prot</i>	the IP protocol of the request
<i>rq_prog</i>	the program number in the request
<i>sv_name</i>	the service name
<i>rq_vers</i>	the program version in the request
<i>peer_ip</i>	the peer address where the request is from
<i>sv_prog</i>	the number of the program
<i>rq_proc</i>	the procedure number in the request

probe::sunrpc.svc.recv

probe::sunrpc.svc.recv — Listen for the next RPC request on any socket

Synopsis

`sunrpc.svc.recv`

Values

sv_nrthreads the number of concurrent threads

timeout the timeout of waiting for data

sv_prog the number of the program

sv_name the service name

probe::sunrpc.svc.register

probe::sunrpc.svc.register — Register an RPC service with the local portmapper

Synopsis

```
sunrpc.svc.register
```

Values

progname the name of the program

port the port number

sv_name the service name

prog the number of the program

prot the IP protocol number

Description

If *proto* and *port* are both 0, then unregister a service.

probe::sunrpc.svc.send

probe::sunrpc.svc.send — Return reply to RPC client

Synopsis

`sunrpc.svc.send`

Values

- rq_prot* the IP protocol of the request
- rq_xid* the transmission id in the request
- peer_ip* the peer address where the request is from
- rq_proc* the procedure number in the request
- rq_prog* the program number in the request
- sv_name* the service name
- rq_vers* the program version in the request

probe::tcp.disconnect

probe::tcp.disconnect — TCP socket disconnection

Synopsis

```
tcp.disconnect
```

Values

sock Network socket

sport TCP source port

dport TCP destination port

family IP address family

name Name of this probe

saddr A string representing the source IP address

daddr A string representing the destination IP address

flags TCP flags (e.g. FIN, etc)

Context

The process which disconnects tcp

probe::tcp.disconnect.return

probe::tcp.disconnect.return — TCP socket disconnection complete

Synopsis

```
tcp.disconnect.return
```

Values

name Name of this probe

ret Error code (0: no error)

Context

The process which disconnects tcp

probe::tcp.receive

probe::tcp.receive — Called when a TCP packet is received

Synopsis

```
tcp.receive
```

Values

<i>sport</i>	TCP source port
<i>dport</i>	TCP destination port
<i>rst</i>	TCP RST flag
<i>fin</i>	TCP FIN flag
<i>syn</i>	TCP SYN flag
<i>daddr</i>	A string representing the destination IP address
<i>saddr</i>	A string representing the source IP address
<i>ack</i>	TCP ACK flag
<i>name</i>	Name of the probe point
<i>urg</i>	TCP URG flag
<i>protocol</i>	Packet protocol from driver
<i>psh</i>	TCP PSH flag
<i>iphdr</i>	IP header address
<i>family</i>	IP address family

probe::tcp.recvmsg

probe::tcp.recvmsg — Receiving TCP message

Synopsis

```
tcp.recvmsg
```

Values

sock Network socket

sport TCP source port

dport TCP destination port

family IP address family

size Number of bytes to be received

saddr A string representing the source IP address

name Name of this probe

daddr A string representing the destination IP address

Context

The process which receives a tcp message

probe::tcp.recvmsg.return

probe::tcp.recvmsg.return — Receiving TCP message complete

Synopsis

```
tcp.recvmsg.return
```

Values

<i>family</i>	IP address family
<i>size</i>	Number of bytes received or error code if an error occurred.
<i>saddr</i>	A string representing the source IP address
<i>name</i>	Name of this probe
<i>daddr</i>	A string representing the destination IP address
<i>sport</i>	TCP source port
<i>dport</i>	TCP destination port

Context

The process which receives a tcp message

probe::tcp.sendmsg

probe::tcp.sendmsg — Sending a tcp message

Synopsis

```
tcp.sendmsg
```

Values

name Name of this probe

family IP address family

sock Network socket

size Number of bytes to send

Context

The process which sends a tcp message

probe::tcp.sendmsg.return

probe::tcp.sendmsg.return — Sending TCP message is done

Synopsis

```
tcp.sendmsg.return
```

Values

name Name of this probe

size Number of bytes sent or error code if an error occurred.

Context

The process which sends a tcp message

probe::tcp.setsockopt

probe::tcp.setsockopt — Call to `setsockopt`

Synopsis

`tcp.setsockopt`

Values

family IP address family

optstr Resolves optname to a human-readable format

optlen Used to access values for `setsockopt`

name Name of this probe

sock Network socket

level The level at which the socket options will be manipulated

optname TCP socket options (e.g. `TCP_NODELAY`, `TCP_MAXSEG`, etc)

Context

The process which calls `setsockopt`

probe::tcp.setsockopt.return

probe::tcp.setsockopt.return — Return from setsockopt

Synopsis

`tcp.setsockopt.return`

Values

ret Error code (0: no error)

name Name of this probe

Context

The process which calls setsockopt

probe::udp.disconnect

probe::udp.disconnect — Fires when a process requests for a UDP disconnection

Synopsis

`udp.disconnect`

Values

<i>saddr</i>	A string representing the source IP address
<i>daddr</i>	A string representing the destination IP address
<i>flags</i>	Flags (e.g. FIN, etc)
<i>sport</i>	UDP source port
<i>name</i>	The name of this probe
<i>dport</i>	UDP destination port
<i>family</i>	IP address family
<i>sock</i>	Network socket used by the process

Context

The process which requests a UDP disconnection

probe::udp.disconnect.return

probe::udp.disconnect.return — UDP has been disconnected successfully

Synopsis

```
udp.disconnect.return
```

Values

name The name of this probe

dport UDP destination port

family IP address family

ret Error code (0: no error)

saddr A string representing the source IP address

daddr A string representing the destination IP address

sport UDP source port

Context

The process which requested a UDP disconnection

probe::udp.recvmsg

probe::udp.recvmsg — Fires whenever a UDP message is received

Synopsis

`udp.recvmsg`

Values

<i>daddr</i>	A string representing the destination IP address
<i>saddr</i>	A string representing the source IP address
<i>sport</i>	UDP source port
<i>name</i>	The name of this probe
<i>dport</i>	UDP destination port
<i>size</i>	Number of bytes received by the process
<i>family</i>	IP address family
<i>sock</i>	Network socket used by the process

Context

The process which received a UDP message

probe::udp.recvmsg.return

probe::udp.recvmsg.return — Fires whenever an attempt to receive a UDP message received is completed

Synopsis

```
udp.recvmsg.return
```

Values

<i>dport</i>	UDP destination port
<i>name</i>	The name of this probe
<i>size</i>	Number of bytes received by the process
<i>family</i>	IP address family
<i>daddr</i>	A string representing the destination IP address
<i>saddr</i>	A string representing the source IP address
<i>sport</i>	UDP source port

Context

The process which received a UDP message

probe::udp.sendmsg

probe::udp.sendmsg — Fires whenever a process sends a UDP message

Synopsis

`udp.sendmsg`

Values

<i>dport</i>	UDP destination port
<i>name</i>	The name of this probe
<i>size</i>	Number of bytes sent by the process
<i>sock</i>	Network socket used by the process
<i>family</i>	IP address family
<i>daddr</i>	A string representing the destination IP address
<i>saddr</i>	A string representing the source IP address
<i>sport</i>	UDP source port

Context

The process which sent a UDP message

probe::udp.sendmsg.return

probe::udp.sendmsg.return — Fires whenever an attempt to send a UDP message is completed

Synopsis

```
udp.sendmsg.return
```

Values

size Number of bytes sent by the process

name The name of this probe

Context

The process which sent a UDP message

Chapter 14. Socket Tapset

This family of probe points is used to probe socket activities. It contains the following probe points:

function::inet_get_ip_source

function::inet_get_ip_source — Provide IP source address string for a kernel socket

Synopsis

```
inet_get_ip_source:string(sock:long)
```

Arguments

sock pointer to the kernel socket

function::inet_get_local_port

function::inet_get_local_port — Provide local port number for a kernel socket

Synopsis

```
inet_get_local_port:long(sock:long)
```

Arguments

sock pointer to the kernel socket

function::sock_fam_num2str

function::sock_fam_num2str — Given a protocol family number, return a string representation

Synopsis

```
sock_fam_num2str:string(family:long)
```

Arguments

family The family number

function::sock_fam_str2num

function::sock_fam_str2num — Given a protocol family name (string), return the corresponding protocol family number

Synopsis

```
sock_fam_str2num:long(family:string)
```

Arguments

family The family name

function::sock_prot_num2str

function::sock_prot_num2str — Given a protocol number, return a string representation

Synopsis

```
sock_prot_num2str:string(proto:long)
```

Arguments

proto The protocol number

function::sock_prot_str2num

function::sock_prot_str2num — Given a protocol name (string), return the corresponding protocol number

Synopsis

```
sock_prot_str2num:long(proto:string)
```

Arguments

proto The protocol name

function::sock_state_num2str

function::sock_state_num2str — Given a socket state number, return a string representation

Synopsis

```
sock_state_num2str:string(state:long)
```

Arguments

state The state number

function::sock_state_str2num

function::sock_state_str2num — Given a socket state string, return the corresponding state number

Synopsis

```
sock_state_str2num:long(state:string)
```

Arguments

state The state name

probe::socket.aio_read

probe::socket.aio_read — Receiving message via `sock_aio_read`

Synopsis

```
socket.aio_read
```

Values

<i>size</i>	Message size in bytes
<i>type</i>	Socket type value
<i>state</i>	Socket state value
<i>name</i>	Name of this probe
<i>family</i>	Protocol family value
<i>flags</i>	Socket flags value
<i>protocol</i>	Protocol value

Context

The message sender

Description

Fires at the beginning of receiving a message on a socket via the `sock_aio_read` function

probe::socket.aio_read.return

probe::socket.aio_read.return — Conclusion of message received via `sock_aio_read`

Synopsis

```
socket.aio_read.return
```

Values

<i>name</i>	Name of this probe
<i>state</i>	Socket state value
<i>size</i>	Size of message received (in bytes) or error code if success = 0
<i>type</i>	Socket type value
<i>success</i>	Was receive successful? (1 = yes, 0 = no)
<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value
<i>family</i>	Protocol family value

Context

The message receiver.

Description

Fires at the conclusion of receiving a message on a socket via the `sock_aio_read` function

probe::socket.aio_write

probe::socket.aio_write — Message send via `sock_aio_write`

Synopsis

```
socket.aio_write
```

Values

<i>name</i>	Name of this probe
<i>type</i>	Socket type value
<i>size</i>	Message size in bytes
<i>state</i>	Socket state value
<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value
<i>family</i>	Protocol family value

Context

The message sender

Description

Fires at the beginning of sending a message on a socket via the `sock_aio_write` function

probe::socket.aio_write.return

probe::socket.aio_write.return — Conclusion of message send via `sock_aio_write`

Synopsis

```
socket.aio_write.return
```

Values

<i>type</i>	Socket type value
<i>size</i>	Size of message received (in bytes) or error code if success = 0
<i>state</i>	Socket state value
<i>name</i>	Name of this probe
<i>family</i>	Protocol family value
<i>flags</i>	Socket flags value
<i>protocol</i>	Protocol value
<i>success</i>	Was receive successful? (1 = yes, 0 = no)

Context

The message receiver.

Description

Fires at the conclusion of sending a message on a socket via the `sock_aio_write` function

probe::socket.close

probe::socket.close — Close a socket

Synopsis

```
socket.close
```

Values

<i>flags</i>	Socket flags value
<i>protocol</i>	Protocol value
<i>family</i>	Protocol family value
<i>name</i>	Name of this probe
<i>state</i>	Socket state value
<i>type</i>	Socket type value

Context

The requester (user process or kernel)

Description

Fires at the beginning of closing a socket.

probe::socket.close.return

probe::socket.close.return — Return from closing a socket

Synopsis

```
socket.close.return
```

Values

name Name of this probe

Context

The requester (user process or kernel)

Description

Fires at the conclusion of closing a socket.

probe::socket.create

probe::socket.create — Creation of a socket

Synopsis

```
socket.create
```

Values

requester Requested by user process or the kernel (1 = kernel, 0 = user)

name Name of this probe

type Socket type value

protocol Protocol value

family Protocol family value

Context

The requester (see requester variable)

Description

Fires at the beginning of creating a socket.

probe::socket.create.return

probe::socket.create.return — Return from Creation of a socket

Synopsis

```
socket.create.return
```

Values

<i>name</i>	Name of this probe
<i>requester</i>	Requested by user process or the kernel (1 = kernel, 0 = user)
<i>type</i>	Socket type value
<i>protocol</i>	Protocol value
<i>err</i>	Error code if success == 0
<i>success</i>	Was socket creation successful? (1 = yes, 0 = no)
<i>family</i>	Protocol family value

Context

The requester (user process or kernel)

Description

Fires at the conclusion of creating a socket.

probe::socket.readv

probe::socket.readv — Receiving a message via `sock_readv`

Synopsis

```
socket.readv
```

Values

<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value
<i>family</i>	Protocol family value
<i>name</i>	Name of this probe
<i>size</i>	Message size in bytes
<i>type</i>	Socket type value
<i>state</i>	Socket state value

Context

The message sender

Description

Fires at the beginning of receiving a message on a socket via the `sock_readv` function

probe::socket.readv.return

probe::socket.readv.return — Conclusion of receiving a message via `sock_readv`

Synopsis

```
socket.readv.return
```

Values

<i>family</i>	Protocol family value
<i>success</i>	Was receive successful? (1 = yes, 0 = no)
<i>flags</i>	Socket flags value
<i>protocol</i>	Protocol value
<i>state</i>	Socket state value
<i>type</i>	Socket type value
<i>size</i>	Size of message received (in bytes) or error code if success = 0
<i>name</i>	Name of this probe

Context

The message receiver.

Description

Fires at the conclusion of receiving a message on a socket via the `sock_readv` function

probe::socket.receive

probe::socket.receive — Message received on a socket.

Synopsis

```
socket.receive
```

Values

<i>name</i>	Name of this probe
<i>state</i>	Socket state value
<i>type</i>	Socket type value
<i>size</i>	Size of message received (in bytes) or error code if success = 0
<i>success</i>	Was send successful? (1 = yes, 0 = no)
<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value
<i>family</i>	Protocol family value

Context

The message receiver

probe::socket.recvmsg

probe::socket.recvmsg — Message being received on socket

Synopsis

```
socket.recvmsg
```

Values

<i>name</i>	Name of this probe
<i>size</i>	Message size in bytes
<i>type</i>	Socket type value
<i>state</i>	Socket state value
<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value
<i>family</i>	Protocol family value

Context

The message receiver.

Description

Fires at the beginning of receiving a message on a socket via the `sock_recvmsg` function

probe::socket.recvmsg.return

probe::socket.recvmsg.return — Return from Message being received on socket

Synopsis

```
socket.recvmsg.return
```

Values

<i>state</i>	Socket state value
<i>type</i>	Socket type value
<i>size</i>	Size of message received (in bytes) or error code if success = 0
<i>name</i>	Name of this probe
<i>family</i>	Protocol family value
<i>success</i>	Was receive successful? (1 = yes, 0 = no)
<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value

Context

The message receiver.

Description

Fires at the conclusion of receiving a message on a socket via the `sock_recvmsg` function.

probe::socket.send

probe::socket.send — Message sent on a socket.

Synopsis

```
socket.send
```

Values

<i>state</i>	Socket state value
<i>type</i>	Socket type value
<i>size</i>	Size of message sent (in bytes) or error code if success = 0
<i>name</i>	Name of this probe
<i>family</i>	Protocol family value
<i>success</i>	Was send successful? (1 = yes, 0 = no)
<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value

Context

The message sender

probe::socket.sendmsg

probe::socket.sendmsg — Message is currently being sent on a socket.

Synopsis

```
socket.sendmsg
```

Values

<i>family</i>	Protocol family value
<i>flags</i>	Socket flags value
<i>protocol</i>	Protocol value
<i>type</i>	Socket type value
<i>size</i>	Message size in bytes
<i>state</i>	Socket state value
<i>name</i>	Name of this probe

Context

The message sender

Description

Fires at the beginning of sending a message on a socket via the `sock_sendmsg` function

probe::socket.sendmsg.return

probe::socket.sendmsg.return — Return from socket.sendmsg.

Synopsis

```
socket.sendmsg.return
```

Values

<i>type</i>	Socket type value
<i>size</i>	Size of message sent (in bytes) or error code if success = 0
<i>state</i>	Socket state value
<i>name</i>	Name of this probe
<i>family</i>	Protocol family value
<i>flags</i>	Socket flags value
<i>protocol</i>	Protocol value
<i>success</i>	Was send successful? (1 = yes, 0 = no)

Context

The message sender.

Description

Fires at the conclusion of sending a message on a socket via the `sock_sendmsg` function

probe::socket.writev

probe::socket.writev — Message sent via `socket_writev`

Synopsis

```
socket.writev
```

Values

<i>name</i>	Name of this probe
<i>size</i>	Message size in bytes
<i>type</i>	Socket type value
<i>state</i>	Socket state value
<i>protocol</i>	Protocol value
<i>flags</i>	Socket flags value
<i>family</i>	Protocol family value

Context

The message sender

Description

Fires at the beginning of sending a message on a socket via the `sock_writev` function

probe::socket.writev.return

probe::socket.writev.return — Conclusion of message sent via `socket_writev`

Synopsis

```
socket.writev.return
```

Values

<i>success</i>	Was send successful? (1 = yes, 0 = no)
<i>flags</i>	Socket flags value
<i>protocol</i>	Protocol value
<i>family</i>	Protocol family value
<i>name</i>	Name of this probe
<i>state</i>	Socket state value
<i>size</i>	Size of message sent (in bytes) or error code if success = 0
<i>type</i>	Socket type value

Context

The message receiver.

Description

Fires at the conclusion of sending a message on a socket via the `sock_writev` function

Chapter 15. SNMP Information Tapset

This family of probe points is used to probe socket activities to provide SNMP type information. It contains the following functions and probe points:

function::ipmib_filter_key

function::ipmib_filter_key — Default filter function for ipmib.* probes

Synopsis

```
ipmib_filter_key:long(skb:long,op:long,SourceIsLocal:long)
```

Arguments

skb pointer to the struct sk_buff

op value to be counted if *skb* passes the filter

SourceIsLocal 1 is local operation and 0 is non-local operation

Description

This function is a default filter function. The user can replace this function with their own. The user-supplied filter function returns an index key based on the values in *skb*. A return value of 0 means this particular *skb* should be not be counted.

function::ipmib_get_proto

function::ipmib_get_proto — Get the protocol value

Synopsis

```
ipmib_get_proto:long(skb:long)
```

Arguments

skb pointer to a struct sk_buff

Description

Returns the protocol value from *skb*.

function::ipmib_local_addr

function::ipmib_local_addr — Get the local ip address

Synopsis

```
ipmib_local_addr:long(skb:long,SourceIsLocal:long)
```

Arguments

skb pointer to a struct sk_buff

SourceIsLocal flag to indicate whether local operation

Description

Returns the local ip address *skb*.

function::ipmib_remote_addr

function::ipmib_remote_addr — Get the remote ip address

Synopsis

```
ipmib_remote_addr:long(skb:long,SourceIsLocal:long)
```

Arguments

skb pointer to a struct sk_buff

SourceIsLocal flag to indicate whether local operation

Description

Returns the remote ip address from *skb*.

function::ipmib_tcp_local_port

function::ipmib_tcp_local_port — Get the local tcp port

Synopsis

```
ipmib_tcp_local_port:long(skb:long,SourceIsLocal:long)
```

Arguments

skb pointer to a struct sk_buff

SourceIsLocal flag to indicate whether local operation

Description

Returns the local tcp port from *skb*.

function::ipmib_tcp_remote_port

function::ipmib_tcp_remote_port — Get the remote tcp port

Synopsis

```
ipmib_tcp_remote_port:long(skb:long,SourceIsLocal:long)
```

Arguments

skb pointer to a struct sk_buff

SourceIsLocal flag to indicate whether local operation

Description

Returns the remote tcp port from *skb*.

function::linuxmib_filter_key

function::linuxmib_filter_key — Default filter function for linuxmib.* probes

Synopsis

```
linuxmib_filter_key:long(sk:long,op:long)
```

Arguments

sk pointer to the struct sock

op value to be counted if *sk* passes the filter

Description

This function is a default filter function. The user can replace this function with their own. The user-supplied filter function returns an index key based on the values in *sk*. A return value of 0 means this particular *sk* should be not be counted.

function::tcpmib_filter_key

function::tcpmib_filter_key — Default filter function for tcpmib.* probes

Synopsis

```
tcpmib_filter_key:long(sk:long,op:long)
```

Arguments

sk pointer to the struct sock being acted on

op value to be counted if *sk* passes the filter

Description

This function is a default filter function. The user can replace this function with their own. The user-supplied filter function returns an index key based on the values in *sk*. A return value of 0 means this particular *sk* should be not be counted.

function::tcpmib_get_state

function::tcpmib_get_state — Get a socket's state

Synopsis

```
tcpmib_get_state:long(sk:long)
```

Arguments

sk pointer to a struct sock

Description

Returns the sk_state from a struct sock.

function::tcpmib_local_addr

function::tcpmib_local_addr — Get the source address

Synopsis

```
tcpmib_local_addr:long(sk:long)
```

Arguments

sk pointer to a struct `inet_sock`

Description

Returns the saddr from a struct `inet_sock` in host order.

function::tcpmib_local_port

function::tcpmib_local_port — Get the local port

Synopsis

```
tcpmib_local_port:long(sk:long)
```

Arguments

sk pointer to a struct `inet_sock`

Description

Returns the sport from a struct `inet_sock` in host order.

function::tcpmib_remote_addr

function::tcpmib_remote_addr — Get the remote address

Synopsis

```
tcpmib_remote_addr:long(sk:long)
```

Arguments

sk pointer to a struct `inet_sock`

Description

Returns the daddr from a struct `inet_sock` in host order.

function::tcpmib_remote_port

function::tcpmib_remote_port — Get the remote port

Synopsis

```
tcpmib_remote_port:long(sk:long)
```

Arguments

sk pointer to a struct `inet_sock`

Description

Returns the dport from a struct `inet_sock` in host order.

probe::ipmib.ForwDatagrams

probe::ipmib.ForwDatagrams — Count forwarded packet

Synopsis

```
ipmib.ForwDatagrams
```

Values

op value to be added to the counter (default value of 1)

skb pointer to the struct sk_buff being acted on

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global `ForwDatagrams` (equivalent to SNMP's MIB `IPSTATS_MIB_OUTFORWDATAGRAMS`)

probe::ipmib.FragFails

probe::ipmib.FragFails — Count datagram fragmented unsuccessfully

Synopsis

```
ipmib.FragFails
```

Values

skb pointer to the struct sk_buff being acted on

op Value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global *FragFails* (equivalent to SNMP's MIB `IPSTATS_MIB_FRAGFAILS`)

probe::ipmib.FragOKs

probe::ipmib.FragOKs — Count datagram fragmented successfully

Synopsis

```
ipmib.FragOKs
```

Values

op value to be added to the counter (default value of 1)

skb pointer to the struct sk_buff being acted on

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global *FragOKs* (equivalent to SNMP's MIB `IPSTATS_MIB_FRAGOKS`)

probe::ipmib.InAddrErrors

probe::ipmib.InAddrErrors — Count arriving packets with an incorrect address

Synopsis

```
ipmib.InAddrErrors
```

Values

op value to be added to the counter (default value of 1)

skb pointer to the struct sk_buff being acted on

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global `InAddrErrors` (equivalent to SNMP's MIB `IPSTATS_MIB_INADDRERRORS`)

probe::ipmib.InDiscards

probe::ipmib.InDiscards — Count discarded inbound packets

Synopsis

```
ipmib.InDiscards
```

Values

op value to be added to the counter (default value of 1)

skb pointer to the struct sk_buff being acted on

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global *InDiscards* (equivalent to SNMP's MIB `STATS_MIB_INDISCARDS`)

probe::ipmib.InNoRoutes

probe::ipmib.InNoRoutes — Count an arriving packet with no matching socket

Synopsis

```
ipmib.InNoRoutes
```

Values

skb pointer to the struct sk_buff being acted on

op value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global *InNoRoutes* (equivalent to SNMP's MIB `IPSTATS_MIB_INNOROUTES`)

probe::ipmib.InReceives

probe::ipmib.InReceives — Count an arriving packet

Synopsis

```
ipmib.InReceives
```

Values

op value to be added to the counter (default value of 1)

skb pointer to the struct sk_buff being acted on

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global `InReceives` (equivalent to SNMP's MIB `IPSTATS_MIB_INRECEIVES`)

probe::ipmib.InUnknownProtos

probe::ipmib.InUnknownProtos — Count arriving packets with an unbound proto

Synopsis

```
ipmib.InUnknownProtos
```

Values

skb pointer to the struct sk_buff being acted on

op value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global `InUnknownProtos` (equivalent to SNMP's MIB `IPSTATS_MIB_INUNKNOWNPROTOS`)

probe::ipmib.OutRequests

probe::ipmib.OutRequests — Count a request to send a packet

Synopsis

```
ipmib.OutRequests
```

Values

op value to be added to the counter (default value of 1)

skb pointer to the struct sk_buff being acted on

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global `OutRequests` (equivalent to SNMP's MIB `IPSTATS_MIB_OUTREQUESTS`)

probe::ipmib.ReasmReqds

probe::ipmib.ReasmReqds — Count number of packet fragments reassembly requests

Synopsis

```
ipmib.ReasmReqds
```

Values

op value to be added to the counter (default value of 1)

skb pointer to the struct sk_buff being acted on

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global `ReasmReqds` (equivalent to SNMP's MIB `IPSTATS_MIB_REASMREQDS`)

probe::ipmib.ReasmTimeout

probe::ipmib.ReasmTimeout — Count Reassembly Timeouts

Synopsis

`ipmib.ReasmTimeout`

Values

skb pointer to the struct `sk_buff` being acted on

op value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `ipmib_filter_key`. If the packet passes the filter it is counted in the global `ReasmTimeout` (equivalent to SNMP's MIB `IPSTATS_MIB_REASMTIMEOUT`)

probe::linuxmib.DelayedACKs

probe::linuxmib.DelayedACKs — Count of delayed acks

Synopsis

```
linuxmib.DelayedACKs
```

Values

sk Pointer to the struct sock being acted on

op Value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `linuxmib_filter_key`. If the packet passes the filter it is counted in the global `DelayedACKs` (equivalent to SNMP's MIB `LINUX_MIB_DELAYEDACKS`)

probe::linuxmib.ListenDrops

probe::linuxmib.ListenDrops — Count of times conn request that were dropped

Synopsis

```
linuxmib.ListenDrops
```

Values

op Value to be added to the counter (default value of 1)

sk Pointer to the struct sock being acted on

Description

The packet pointed to by *skb* is filtered by the function `linuxmib_filter_key`. If the packet passes the filter it is counted in the global `ListenDrops` (equivalent to SNMP's MIB `LINUX_MIB_LISTENDROPS`)

probe::linuxmib.ListenOverflows

probe::linuxmib.ListenOverflows — Count of times a listen queue overflowed

Synopsis

```
linuxmib.ListenOverflows
```

Values

sk Pointer to the struct sock being acted on

op Value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `linuxmib_filter_key`. If the packet passes the filter it is counted in the global `ListenOverflows` (equivalent to SNMP's MIB `LINUX_MIB_LISTENOVERFLOWS`)

probe::linuxmib.TCPMemoryPressures

probe::linuxmib.TCPMemoryPressures — Count of times memory pressure was used

Synopsis

```
linuxmib.TCPMemoryPressures
```

Values

op Value to be added to the counter (default value of 1)

sk Pointer to the struct sock being acted on

Description

The packet pointed to by *skb* is filtered by the function `linuxmib_filter_key`. If the packet passes the filter it is counted in the global `TCPMemoryPressures` (equivalent to SNMP's MIB `LINUX_MIB_TCPMEMORYPRESSURES`)

probe::tcpmib.ActiveOpens

probe::tcpmib.ActiveOpens — Count an active opening of a socket

Synopsis

```
tcpmib.ActiveOpens
```

Values

op value to be added to the counter (default value of 1)

sk pointer to the struct sock being acted on

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global `ActiveOpens` (equivalent to SNMP's MIB `TCP_MIB_ACTIVEOPENS`)

probe::tcpmib.AttemptFails

probe::tcpmib.AttemptFails — Count a failed attempt to open a socket

Synopsis

```
tcpmib.AttemptFails
```

Values

sk pointer to the struct sock being acted on

op value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global `AttemptFails` (equivalent to SNMP's MIB `TCP_MIB_ATTEMPTFAILS`)

probe::tcpmib.CurrEstab

probe::tcpmib.CurrEstab — Update the count of open sockets

Synopsis

```
tcpmib.CurrEstab
```

Values

op value to be added to the counter (default value of 1)

sk pointer to the struct sock being acted on

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global *CurrEstab* (equivalent to SNMP's MIB `TCP_MIB_CURRESTAB`)

probe::tcpmib.EstabResets

probe::tcpmib.EstabResets — Count the reset of a socket

Synopsis

```
tcpmib.EstabResets
```

Values

sk pointer to the struct sock being acted on

op value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global `EstabResets` (equivalent to SNMP's MIB `TCP_MIB_ESTABRESETS`)

probe::tcpmib.InSegs

probe::tcpmib.InSegs — Count an incoming tcp segment

Synopsis

`tcpmib.InSegs`

Values

op value to be added to the counter (default value of 1)

sk pointer to the struct sock being acted on

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key` (or `ipmib_filter_key` for tcp v4). If the packet passes the filter it is counted in the global *InSegs* (equivalent to SNMP's MIB TCP_MIB_INSEGS)

probe::tcpmib.OutRsts

probe::tcpmib.OutRsts — Count the sending of a reset packet

Synopsis

`tcpmib.OutRsts`

Values

op value to be added to the counter (default value of 1)

sk pointer to the struct sock being acted on

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global *OutRsts* (equivalent to SNMP's MIB `TCP_MIB_OUTRSTS`)

probe::tcpmib.OutSegs

probe::tcpmib.OutSegs — Count the sending of a TCP segment

Synopsis

```
tcpmib.OutSegs
```

Values

op value to be added to the counter (default value of 1)

sk pointer to the struct sock being acted on

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global *OutSegs* (equivalent to SNMP's MIB `TCP_MIB_OUTSEGS`)

probe::tcpmib.PassiveOpens

probe::tcpmib.PassiveOpens — Count the passive creation of a socket

Synopsis

`tcpmib.PassiveOpens`

Values

sk pointer to the struct sock being acted on

op value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global *PassiveOpens* (equivalent to SNMP's MIB `TCP_MIB_PASSIVEOPENS`)

probe::tcpmib.RetransSegs

probe::tcpmib.RetransSegs — Count the retransmission of a TCP segment

Synopsis

```
tcpmib.RetransSegs
```

Values

sk pointer to the struct sock being acted on

op value to be added to the counter (default value of 1)

Description

The packet pointed to by *skb* is filtered by the function `tcpmib_filter_key`. If the packet passes the filter it is counted in the global *RetransSegs* (equivalent to SNMP's MIB `TCP_MIB_RETRANSSEGS`)

Chapter 16. Kernel Process Tapset

This family of probe points is used to probe process-related activities. It contains the following probe points:

function::target_set_pid

function::target_set_pid — Does pid descend from target process?

Synopsis

```
target_set_pid(pid: )
```

Arguments

pid The pid of the process to query

Description

This function returns whether the given process-id is within the “target set”, that is whether it is a descendant of the top-level target process.

function::target_set_report

function::target_set_report — Print a report about the target set

Synopsis

```
target_set_report()
```

Arguments

None

Description

This function prints a report about the processes in the target set, and their ancestry.

probe::kprocess.create

probe::kprocess.create — Fires whenever a new process or thread is successfully created

Synopsis

```
kprocess.create
```

Values

new_pid The PID of the newly created process

new_tid The TID of the newly created task

Context

Parent of the created process.

Description

Fires whenever a new process is successfully created, either as a result of fork (or one of its syscall variants), or a new kernel thread.

probe::kprocess.exec

`probe::kprocess.exec` — Attempt to exec to a new program

Synopsis

`kprocess.exec`

Values

filename The path to the new executable

Context

The caller of exec.

Description

Fires whenever a process attempts to exec to a new program.

probe::kprocess.exec_complete

probe::kprocess.exec_complete — Return from exec to a new program

Synopsis

```
kprocess.exec_complete
```

Values

success A boolean indicating whether the exec was successful

errno The error number resulting from the exec

Context

On success, the context of the new executable. On failure, remains in the context of the caller.

Description

Fires at the completion of an exec call.

probe::kprocess.exit

probe::kprocess.exit — Exit from process

Synopsis

```
kprocess.exit
```

Values

code The exit code of the process

Context

The process which is terminating.

Description

Fires when a process terminates. This will always be followed by a kprocess.release, though the latter may be delayed if the process waits in a zombie state.

probe::kprocess.release

probe::kprocess.release — Process released

Synopsis

```
kprocess.release
```

Values

released_pid PID of the process being released

pid Same as *released_pid* for compatibility (deprecated)

released_tid TID of the task being released

task A task handle to the process being released

Context

The context of the parent, if it wanted notification of this process' termination, else the context of the process itself.

Description

Fires when a process is released from the kernel. This always follows a kprocess.exit, though it may be delayed somewhat if the process waits in a zombie state.

probe::kprocess.start

probe::kprocess.start — Starting new process

Synopsis

`kprocess.start`

Values

None

Context

Newly created process.

Description

Fires immediately before a new process begins execution.

Chapter 17. Signal Tapset

This family of probe points is used to probe signal activities. It contains the following probe points:

function::get_sa_flags

function::get_sa_flags — Returns the numeric value of sa_flags

Synopsis

```
get_sa_flags:long(act:long)
```

Arguments

act address of the sigaction to query.

function::get_sa_handler

function::get_sa_handler — Returns the numeric value of sa_handler

Synopsis

```
get_sa_handler:long(act:long)
```

Arguments

act address of the sigaction to query.

function::is_sig_blocked

function::is_sig_blocked — Returns 1 if the signal is currently blocked, or 0 if it is not

Synopsis

```
is_sig_blocked:long(task:long,sig:long)
```

Arguments

task address of the task_struct to query.

sig the signal number to test.

function::sa_flags_str

function::sa_flags_str — Returns the string representation of sa_flags

Synopsis

```
sa_flags_str:string(sa_flags:long)
```

Arguments

sa_flags the set of flags to convert to string.

function::sa_handler_str

function::sa_handler_str — Returns the string representation of an sa_handler

Synopsis

```
sa_handler_str(handler:)
```

Arguments

handler the sa_handler to convert to string.

Description

Returns the string representation of an sa_handler. If it is not SIG_DFL, SIG_IGN or SIG_ERR, it will return the address of the handler.

function::signal_str

function::signal_str — Returns the string representation of a signal number

Synopsis

```
signal_str(num:)
```

Arguments

num the signal number to convert to string.

function::sigset_mask_str

function::sigset_mask_str — Returns the string representation of a sigset

Synopsis

```
sigset_mask_str:string(mask:long)
```

Arguments

mask the sigset to convert to string.

probe::signal.check_ignored

probe::signal.check_ignored — Checking to see signal is ignored

Synopsis

```
signal.check_ignored
```

Values

sig_name A string representation of the signal

sig The number of the signal

sig_pid The PID of the process receiving the signal

pid_name Name of the process receiving the signal

probe::signal.check_ignored.return

probe::signal.check_ignored.return — Check to see signal is ignored completed

Synopsis

```
signal.check_ignored.return
```

Values

retstr Return value as a string

name Name of the probe point

probe::signal.checkperm

probe::signal.checkperm — Check being performed on a sent signal

Synopsis

```
signal.checkperm
```

Values

<i>task</i>	A task handle to the signal recipient
<i>pid_name</i>	Name of the process receiving the signal
<i>si_code</i>	Indicates the signal type
<i>sig_name</i>	A string representation of the signal
<i>sinfo</i>	The address of the siginfo structure
<i>sig</i>	The number of the signal
<i>name</i>	Name of the probe point
<i>sig_pid</i>	The PID of the process receiving the signal

probe::signal.checkperm.return

probe::signal.checkperm.return — Check performed on a sent signal completed

Synopsis

```
signal.checkperm.return
```

Values

name Name of the probe point

retstr Return value as a string

probe::signal.do_action

probe::signal.do_action — Examining or changing a signal action

Synopsis

```
signal.do_action
```

Values

<i>sigact_addr</i>	The address of the new sigaction struct associated with the signal
<i>oldsigact_addr</i>	The address of the old sigaction struct associated with the signal
<i>sig</i>	The signal to be examined/changed
<i>name</i>	Name of the probe point
<i>sa_handler</i>	The new handler of the signal
<i>sa_mask</i>	The new mask of the signal
<i>sig_name</i>	A string representation of the signal

probe::signal.do_action.return

probe::signal.do_action.return — Examining or changing a signal action completed

Synopsis

```
signal.do_action.return
```

Values

retstr Return value as a string

name Name of the probe point

probe::signal.flush

probe::signal.flush — Flushing all pending signals for a task

Synopsis

```
signal.flush
```

Values

sig_pid The PID of the process associated with the task performing the flush

name Name of the probe point

task The task handler of the process performing the flush

pid_name The name of the process associated with the task performing the flush

probe::signal.force_segv

probe::signal.force_segv — Forcing send of SIGSEGV

Synopsis

```
signal.force_segv
```

Values

pid_name Name of the process receiving the signal

sig_name A string representation of the signal

sig The number of the signal

name Name of the probe point

sig_pid The PID of the process receiving the signal

probe::signal.force_segv.return

probe::signal.force_segv.return — Forcing send of SIGSEGV complete

Synopsis

```
signal.force_segv.return
```

Values

name Name of the probe point

retstr Return value as a string

probe::signal.handle

probe::signal.handle — Signal handler being invoked

Synopsis

```
signal.handle
```

Values

<i>sig_code</i>	The si_code value of the siginfo signal
<i>oldset_addr</i>	The address of the bitmask array of blocked signals (deprecated in SystemTap 2.1)
<i>regs</i>	The address of the kernel-mode stack area (deprecated in SystemTap 2.1)
<i>sinfo</i>	The address of the siginfo table
<i>sig_name</i>	A string representation of the signal
<i>sig_mode</i>	Indicates whether the signal was a user-mode or kernel-mode signal
<i>name</i>	Name of the probe point
<i>ka_addr</i>	The address of the k_sigaction table associated with the signal
<i>sig</i>	The signal number that invoked the signal handler

probe::signal.handle.return

probe::signal.handle.return — Signal handler invocation completed

Synopsis

```
signal.handle.return
```

Values

name Name of the probe point

retstr Return value as a string

Description

(deprecated in SystemTap 2.1)

probe::signal.pending

probe::signal.pending — Examining pending signal

Synopsis

```
signal.pending
```

Values

sigset_size The size of the user-space signal set

sigset_add The address of the user-space signal set (sigset_t)

name Name of the probe point

Description

This probe is used to examine a set of signals pending for delivery to a specific thread. This normally occurs when the do_sigpending kernel function is executed.

probe::signal.pending.return

probe::signal.pending.return — Examination of pending signal completed

Synopsis

```
signal.pending.return
```

Values

retstr Return value as a string

name Name of the probe point

probe::signal.procmask

probe::signal.procmask — Examining or changing blocked signals

Synopsis

```
signal.procmask
```

Values

<i>sigset_addr</i>	The address of the signal set (sigset_t) to be implemented
<i>oldsigset_addr</i>	The old address of the signal set (sigset_t)
<i>name</i>	Name of the probe point
<i>sigset</i>	The actual value to be set for sigset_t (correct?)
<i>how</i>	Indicates how to change the blocked signals; possible values are SIG_BLOCK=0 (for blocking signals), SIG_UNBLOCK=1 (for unblocking signals), and SIG_SETMASK=2 for setting the signal mask.

probe::signal.procmask.return

probe::signal.procmask.return — Examining or changing blocked signals completed

Synopsis

```
signal.procmask.return
```

Values

name Name of the probe point

retstr Return value as a string

probe::signal.send

probe::signal.send — Signal being sent to a process

Synopsis

```
signal.send
```

Values

<i>task</i>	A task handle to the signal recipient
<i>pid_name</i>	The name of the signal recipient
<i>shared</i>	Indicates whether the signal is shared by the thread group
<i>sig_name</i>	A string representation of the signal
<i>si_code</i>	Indicates the signal type
<i>send2queue</i>	Indicates whether the signal is sent to an existing sigqueue (deprecated in SystemTap 2.1)
<i>sinfo</i>	The address of siginfo struct
<i>sig_pid</i>	The PID of the process receiving the signal
<i>name</i>	The name of the function used to send out the signal
<i>sig</i>	The number of the signal

Context

The signal's sender.

probe::signal.send.return

probe::signal.send.return — Signal being sent to a process completed (deprecated in SystemTap 2.1)

Synopsis

```
signal.send.return
```

Values

<i>shared</i>	Indicates whether the sent signal is shared by the thread group.
<i>retstr</i>	The return value to either __group_send_sig_info, specific_send_sig_info, or send_sigqueue
<i>name</i>	The name of the function used to send out the signal
<i>send2queue</i>	Indicates whether the sent signal was sent to an existing sigqueue

Context

The signal's sender. (correct?)

Description

Possible __group_send_sig_info and specific_send_sig_info return values are as follows;

0 -- The signal is successfully sent to a process, which means that, (1) the signal was ignored by the receiving process, (2) this is a non-RT signal and the system already has one queued, and (3) the signal was successfully added to the sigqueue of the receiving process.

-EAGAIN -- The sigqueue of the receiving process is overflowing, the signal was RT, and the signal was sent by a user using something other than kill.

Possible send_group_sigqueue and send_sigqueue return values are as follows;

0 -- The signal was either successfully added into the sigqueue of the receiving process, or a SI_TIMER entry is already queued (in which case, the overrun count will be simply incremented).

1 -- The signal was ignored by the receiving process.

-1 -- (send_sigqueue only) The task was marked exiting, allowing * posix_timer_event to redirect it to the group leader.

probe::signal.send_sig_queue

probe::signal.send_sig_queue — Queuing a signal to a process

Synopsis

```
signal.send_sig_queue
```

Values

<i>pid_name</i>	Name of the process to which the signal is queued
<i>sig_name</i>	A string representation of the signal
<i>sigqueue_addr</i>	The address of the signal queue
<i>sig</i>	The queued signal
<i>name</i>	Name of the probe point
<i>sig_pid</i>	The PID of the process to which the signal is queued

probe::signal.send_sig_queue.return

probe::signal.send_sig_queue.return — Queuing a signal to a process completed

Synopsis

```
signal.send_sig_queue.return
```

Values

name Name of the probe point

retstr Return value as a string

probe::signal.sys_tgkill

probe::signal.sys_tgkill — Sending kill signal to a thread group

Synopsis

```
signal.sys_tgkill
```

Values

<i>sig</i>	The specific kill signal sent to the process
<i>name</i>	Name of the probe point
<i>sig_pid</i>	The PID of the thread receiving the kill signal
<i>sig_name</i>	A string representation of the signal
<i>pid_name</i>	The name of the signal recipient
<i>tgid</i>	The thread group ID of the thread receiving the kill signal

Description

The tgkill call is similar to tkill, except that it also allows the caller to specify the thread group ID of the thread to be signalled. This protects against TID reuse.

probe::signal.sys_tgkill.return

probe::signal.sys_tgkill.return — Sending kill signal to a thread group completed

Synopsis

```
signal.sys_tgkill.return
```

Values

name Name of the probe point

retstr The return value to either __group_send_sig_info,

probe::signal.sys_tkill

probe::signal.sys_tkill — Sending a kill signal to a thread

Synopsis

```
signal.sys_tkill
```

Values

sig_name A string representation of the signal

sig_pid The PID of the process receiving the kill signal

name Name of the probe point

sig The specific signal sent to the process

pid_name The name of the signal recipient

Description

The tkill call is analogous to kill(2), except that it also allows a process within a specific thread group to be targeted. Such processes are targeted through their unique thread IDs (TID).

probe::signal.syskill

probe::signal.syskill — Sending kill signal to a process

Synopsis

```
signal.syskill
```

Values

<i>sig_name</i>	A string representation of the signal
<i>sig</i>	The specific signal sent to the process
<i>name</i>	Name of the probe point
<i>sig_pid</i>	The PID of the process receiving the signal
<i>pid_name</i>	The name of the signal recipient

probe::signal.syskill.return

probe::signal.syskill.return — Sending kill signal completed

Synopsis

```
signal.syskill.return
```

Values

None

probe::signal.systkill.return

probe::signal.systkill.return — Sending kill signal to a thread completed

Synopsis

```
signal.systkill.return
```

Values

retstr The return value to either __group_send_sig_info,

name Name of the probe point

probe::signal.wakeup

probe::signal.wakeup — Sleeping process being wakened for signal

Synopsis

```
signal.wakeup
```

Values

<i>sig_pid</i>	The PID of the process to wake
<i>state_mask</i>	A string representation indicating the mask of task states to wake. Possible values are TASK_INTERRUPTIBLE, TASK_STOPPED, TASK_TRACED, TASK_WAKEKILL, and TASK_INTERRUPTIBLE.
<i>resume</i>	Indicates whether to wake up a task in a STOPPED or TRACED state
<i>pid_name</i>	Name of the process to wake

Chapter 18. Errno Tapset

This set of functions is used to handle errno number values. It contains the following functions:

function::errno_str

function::errno_str — Symbolic string associated with error code

Synopsis

```
errno_str:string(err:long)
```

Arguments

err The error number received

Description

This function returns the symbolic string associated with the given error code, such as ENOENT for the number 2, or E#3333 for an out-of-range value such as 3333.

function::return_str

function::return_str — Formats the return value as a string

Synopsis

```
return_str:string(format:long,ret:long)
```

Arguments

format Variable to determine return type base value

ret Return value (typically \$return)

Description

This function is used by the syscall tapset, and returns a string. Set format equal to 1 for a decimal, 2 for hex, 3 for octal.

Note that this function is preferred over `returnstr`.

function::returnstr

function::returnstr — Formats the return value as a string

Synopsis

```
returnstr:string(format:long)
```

Arguments

format Variable to determine return type base value

Description

This function is used by the nd_syscall tapset, and returns a string. Set format equal to 1 for a decimal, 2 for hex, 3 for octal.

Note that this function should only be used in dwarfless probes (i.e. 'kprobe.function("foo")'). Other probes should use `return_str`.

function::returnval

function::returnval — Possible return value of probed function

Synopsis

```
returnval:long()
```

Arguments

None

Description

Return the value of the register in which function values are typically returned. Can be used in probes where \$return isn't available. This is only a guess of the actual return value and can be totally wrong. Normally only used in dwarfless probes.

Chapter 19. Device Tapset

This set of functions is used to handle kernel and userspace device numbers. It contains the following functions:

function::MAJOR

function::MAJOR — Extract major device number from a kernel device number (kdev_t)

Synopsis

```
MAJOR:long(dev:long)
```

Arguments

dev Kernel device number to query.

function::MINOR

function::MINOR — Extract minor device number from a kernel device number (kdev_t)

Synopsis

```
MINOR:long(dev:long)
```

Arguments

dev Kernel device number to query.

function::MKDEV

function::MKDEV — Creates a value that can be compared to a kernel device number (kdev_t)

Synopsis

```
MKDEV:long(major:long,minor:long)
```

Arguments

major Intended major device number.

minor Intended minor device number.

function::usrdev2kerndev

function::usrdev2kerndev — Converts a user-space device number into the format used in the kernel

Synopsis

```
usrdev2kerndev:long(dev:long)
```

Arguments

dev Device number in user-space format.

Chapter 20. Directory-entry (dentry) Tapset

This family of functions is used to map kernel VFS directory entry pointers to file or full path names.

function::d_name

function::d_name — get the dirent name

Synopsis

```
d_name:string(dentry:long)
```

Arguments

dentry Pointer to dentry.

Description

Returns the dirent name (path basename).

function::d_path

function::d_path — get the full nameidata path

Synopsis

```
d_path:string(nd:long)
```

Arguments

nd Pointer to nameidata.

Description

Returns the full dirent name (full path to the root), like the kernel d_path function.

function::inode_name

function::inode_name — get the inode name

Synopsis

```
inode_name:string(inode:long)
```

Arguments

inode Pointer to inode.

Description

Returns the first path basename associated with the given inode.

function::real_mount

function::real_mount — get the 'struct mount' pointer

Synopsis

```
real_mount:long(vfsmnt:long)
```

Arguments

vfsmnt Pointer to 'struct vfsmount'

Description

Returns the 'struct mount' pointer value for a 'struct vfsmount' pointer.

function::reverse_path_walk

function::reverse_path_walk — get the full dirent path

Synopsis

```
reverse_path_walk:string(dentry:long)
```

Arguments

dentry Pointer to dentry.

Description

Returns the path name (partial path to mount point).

function::task_dentry_path

function::task_dentry_path — get the full dentry path

Synopsis

```
task_dentry_path:string(task:long,dentry:long,vfsmnt:long)
```

Arguments

task task_struct pointer.

dentry direntry pointer.

vfsmnt vfsmnt pointer.

Description

Returns the full dirent name (full path to the root), like the kernel d_path function.

Chapter 21. Logging Tapset

This family of functions is used to send simple message strings to various destinations.

function::error

function::error — Send an error message

Synopsis

```
error(msg:string)
```

Arguments

msg The formatted message string

Description

An implicit end-of-line is added. staprun prepends the string “ERROR:”. Sending an error message aborts the currently running probe. Depending on the MAXERRORS parameter, it may trigger an exit.

function::exit

function::exit — Start shutting down probing script.

Synopsis

```
exit( )
```

Arguments

None

Description

This only enqueues a request to start shutting down the script. New probes will not fire (except “end” probes), but all currently running ones may complete their work.

function::ftrace

function::ftrace — Send a message to the ftrace ring-buffer

Synopsis

```
ftrace(msg:string)
```

Arguments

msg The formatted message string

Description

If the ftrace ring-buffer is configured & available, see /debugfs/tracing/trace for the message. Otherwise, the message may be quietly dropped. An implicit end-of-line is added.

function::log

function::log — Send a line to the common trace buffer

Synopsis

```
log(msg:string)
```

Arguments

msg The formatted message string

Description

This function logs data. log sends the message immediately to staprund and to the bulk transport (relayfs) if it is being used. If the last character given is not a newline, then one is added. This function is not as efficient as printf and should be used only for urgent messages.

function::printf

function::printf — Send a message to the kernel trace buffer

Synopsis

```
printf(level:long,msg:string)
```

Arguments

level an integer for the severity level (0=KERN_EMERG ... 7=KERN_DEBUG)

msg The formatted message string

Description

Print a line of text to the kernel dmesg/console with the given severity. An implicit end-of-line is added. This function may not be safely called from all kernel probe contexts, so is restricted to guru mode only.

function::warn

function::warn — Send a line to the warning stream

Synopsis

```
warn(msg:string)
```

Arguments

msg The formatted message string

Description

This function sends a warning message immediately to staprund. It is also sent over the bulk transport (relayfs) if it is being used. If the last character is not a newline, the one is added.

Chapter 22. Queue Statistics Tapset

This family of functions is used to track performance of queuing systems.

function::qs_done

function::qs_done — Function to record finishing request

Synopsis

```
qs_done(qname:string)
```

Arguments

qname the name of the service that finished

Description

This function records that a request originally from the given queue has completed being serviced.

function::qs_run

function::qs_run — Function to record being moved from wait queue to being serviced

Synopsis

```
qs_run(qname:string)
```

Arguments

qname the name of the service being moved and started

Description

This function records that the previous enqueued request was removed from the given wait queue and is now being serviced.

function::qs_wait

function::qs_wait — Function to record enqueue requests

Synopsis

```
qs_wait(qname:string)
```

Arguments

qname the name of the queue requesting enqueue

Description

This function records that a new request was enqueued for the given queue name.

function:::qsq_blocked

function:::qsq_blocked — Returns the time request was on the wait queue

Synopsis

```
qsq_blocked:long(qname:string,scale:long)
```

Arguments

qname queue name

scale scale variable to take account for interval fraction

Description

This function returns the fraction of elapsed time during which one or more requests were on the wait queue.

function:::qsq_print

function:::qsq_print — Prints a line of statistics for the given queue

Synopsis

```
qsq_print(qname:string)
```

Arguments

qname queue name

Description

This function prints a line containing the following

statistics for the given queue

the queue name, the average rate of requests per second, the average wait queue length, the average time on the wait queue, the average time to service a request, the percentage of time the wait queue was used, and the percentage of time request was being serviced.

function:::qsq_service_time

function:::qsq_service_time — Amount of time per request service

Synopsis

```
qsq_service_time:long(qname:string,scale:long)
```

Arguments

qname queue name

scale scale variable to take account for interval fraction

Description

This function returns the average time in microseconds required to service a request once it is removed from the wait queue.

function::qsq_start

function::qsq_start — Function to reset the stats for a queue

Synopsis

```
qsq_start(qname:string)
```

Arguments

qname the name of the service that finished

Description

This function resets the statistics counters for the given queue, and restarts tracking from the moment the function was called. This function is also used to create initialize a queue.

function:::qsq_throughput

function:::qsq_throughput — Number of requests served per unit time

Synopsis

```
qsq_throughput:long(qname:string,scale:long)
```

Arguments

qname queue name

scale scale variable to take account for interval fraction

Description

This function returns the average number of requests served per microsecond.

function::qsq_utilization

function::qsq_utilization — Fraction of time that any request was being serviced

Synopsis

```
qsq_utilization:long(qname:string,scale:long)
```

Arguments

qname queue name

scale scale variable to take account for interval fraction

Description

This function returns the average time in microseconds that at least one request was being serviced.

function:::qsq_wait_queue_length

function:::qsq_wait_queue_length — length of wait queue

Synopsis

```
qsq_wait_queue_length:long(qname:string,scale:long)
```

Arguments

qname queue name

scale scale variable to take account for interval fraction

Description

This function returns the average length of the wait queue

function:::qsq_wait_time

function:::qsq_wait_time — Amount of time in queue + service per request

Synopsis

```
qsq_wait_time:long(qname:string,scale:long)
```

Arguments

qname queue name

scale scale variable to take account for interval fraction

Description

This function returns the average time in microseconds that it took for a request to be serviced (qs_wait to qa_done).

Chapter 23. Random functions Tapset

These functions deal with random number generation.

function::randint

function::randint — Return a random number between [0,n)

Synopsis

```
randint:long(n:long)
```

Arguments

n Number past upper limit of range, not larger than 2**20.

Chapter 24. String and data retrieving functions Tapset

Functions to retrieve strings and other primitive types from the kernel or a user space programs based on addresses. All strings are of a maximum length given by MAXSTRINGLEN.

function::atomic_long_read

function::atomic_long_read — Retrieves an atomic long variable from kernel memory

Synopsis

```
atomic_long_read:long(addr:long)
```

Arguments

addr pointer to atomic long variable

Description

Safely perform the read of an atomic long variable. This will be a NOP on kernels that do not have ATOMIC_LONG_INIT set on the kernel config.

function::atomic_read

function::atomic_read — Retrieves an atomic variable from kernel memory

Synopsis

```
atomic_read:long(addr:long)
```

Arguments

addr pointer to atomic variable

Description

Safely perform the read of an atomic variable.

function::kernel_char

function::kernel_char — Retrieves a char value stored in kernel memory

Synopsis

```
kernel_char:long(addr:long)
```

Arguments

addr The kernel address to retrieve the char from

Description

Returns the char value from a given kernel memory address. Reports an error when reading from the given address fails.

function::kernel_int

function::kernel_int — Retrieves an int value stored in kernel memory

Synopsis

```
kernel_int:long(addr:long)
```

Arguments

addr The kernel address to retrieve the int from

Description

Returns the int value from a given kernel memory address. Reports an error when reading from the given address fails.

function::kernel_long

function::kernel_long — Retrieves a long value stored in kernel memory

Synopsis

```
kernel_long:long(addr:long)
```

Arguments

addr The kernel address to retrieve the long from

Description

Returns the long value from a given kernel memory address. Reports an error when reading from the given address fails.

function::kernel_pointer

function::kernel_pointer — Retrieves a pointer value stored in kernel memory

Synopsis

```
kernel_pointer:long(addr:long)
```

Arguments

addr The kernel address to retrieve the pointer from

Description

Returns the pointer value from a given kernel memory address. Reports an error when reading from the given address fails.

function::kernel_short

function::kernel_short — Retrieves a short value stored in kernel memory

Synopsis

```
kernel_short:long(addr:long)
```

Arguments

addr The kernel address to retrieve the short from

Description

Returns the short value from a given kernel memory address. Reports an error when reading from the given address fails.

function::kernel_string

function::kernel_string — Retrieves string from kernel memory

Synopsis

```
kernel_string:string(addr:long)
```

Arguments

addr The kernel address to retrieve the string from

Description

This function returns the null terminated C string from a given kernel memory address. Reports an error on string copy fault.

function::kernel_string2

function::kernel_string2 — Retrieves string from kernel memory with alternative error string

Synopsis

```
kernel_string2:string(addr:long,err_msg:string)
```

Arguments

addr The kernel address to retrieve the string from

err_msg The error message to return when data isn't available

Description

This function returns the null terminated C string from a given kernel memory address. Reports the given error message on string copy fault.

function::kernel_string2_utf16

function::kernel_string2_utf16 — Retrieves UTF-16 string from kernel memory with alternative error string

Synopsis

```
kernel_string2_utf16:string(addr:long,err_msg:string)
```

Arguments

addr The kernel address to retrieve the string from

err_msg The error message to return when data isn't available

Description

This function returns a null terminated UTF-8 string converted from the UTF-16 string at a given kernel memory address. Reports the given error message on string copy fault or conversion error.

function::kernel_string2_utf32

function::kernel_string2_utf32 — Retrieves UTF-32 string from kernel memory with alternative error string

Synopsis

```
kernel_string2_utf32:string(addr:long,err_msg:string)
```

Arguments

addr The kernel address to retrieve the string from

err_msg The error message to return when data isn't available

Description

This function returns a null terminated UTF-8 string converted from the UTF-32 string at a given kernel memory address. Reports the given error message on string copy fault or conversion error.

function::kernel_string_n

function::kernel_string_n — Retrieves string of given length from kernel memory

Synopsis

```
kernel_string_n:string(addr:long,n:long)
```

Arguments

addr The kernel address to retrieve the string from

n The maximum length of the string (if not null terminated)

Description

Returns the C string of a maximum given length from a given kernel memory address. Reports an error on string copy fault.

function::kernel_string_utf16

function::kernel_string_utf16 — Retrieves UTF-16 string from kernel memory

Synopsis

```
kernel_string_utf16:string(addr:long)
```

Arguments

addr The kernel address to retrieve the string from

Description

This function returns a null terminated UTF-8 string converted from the UTF-16 string at a given kernel memory address. Reports an error on string copy fault or conversion error.

function::kernel_string_utf32

function::kernel_string_utf32 — Retrieves UTF-32 string from kernel memory

Synopsis

```
kernel_string_utf32:string(addr:long)
```

Arguments

addr The kernel address to retrieve the string from

Description

This function returns a null terminated UTF-8 string converted from the UTF-32 string at a given kernel memory address. Reports an error on string copy fault or conversion error.

function::user_char

function::user_char — Retrieves a char value stored in user space

Synopsis

```
user_char:long(addr:long)
```

Arguments

addr the user space address to retrieve the char from

Description

Returns the char value from a given user space address. Returns zero when user space data is not accessible.

function::user_char_warn

function::user_char_warn — Retrieves a char value stored in user space

Synopsis

```
user_char_warn:long(addr:long)
```

Arguments

addr the user space address to retrieve the char from

Description

Returns the char value from a given user space address. Returns zero when user space and warns (but does not abort) about the failure.

function::user_int

function::user_int — Retrieves an int value stored in user space

Synopsis

```
user_int:long(addr:long)
```

Arguments

addr the user space address to retrieve the int from

Description

Returns the int value from a given user space address. Returns zero when user space data is not accessible.

function::user_int16

function::user_int16 — Retrieves a 16-bit integer value stored in user space

Synopsis

```
user_int16:long(addr:long)
```

Arguments

addr the user space address to retrieve the 16-bit integer from

Description

Returns the 16-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_int32

function::user_int32 — Retrieves a 32-bit integer value stored in user space

Synopsis

```
user_int32:long(addr:long)
```

Arguments

addr the user space address to retrieve the 32-bit integer from

Description

Returns the 32-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_int64

function::user_int64 — Retrieves a 64-bit integer value stored in user space

Synopsis

```
user_int64:long(addr:long)
```

Arguments

addr the user space address to retrieve the 64-bit integer from

Description

Returns the 64-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_int8

function::user_int8 — Retrieves a 8-bit integer value stored in user space

Synopsis

```
user_int8:long(addr:long)
```

Arguments

addr the user space address to retrieve the 8-bit integer from

Description

Returns the 8-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_int_warn

function::user_int_warn — Retrieves an int value stored in user space

Synopsis

```
user_int_warn:long(addr:long)
```

Arguments

addr the user space address to retrieve the int from

Description

Returns the int value from a given user space address. Returns zero when user space and warns (but does not abort) about the failure.

function::user_long

function::user_long — Retrieves a long value stored in user space

Synopsis

```
user_long:long(addr:long)
```

Arguments

addr the user space address to retrieve the long from

Description

Returns the long value from a given user space address. Returns zero when user space data is not accessible. Note that the size of the long depends on the architecture of the current user space task (for those architectures that support both 64/32 bit compat tasks).

function::user_long_warn

function::user_long_warn — Retrieves a long value stored in user space

Synopsis

```
user_long_warn:long(addr:long)
```

Arguments

addr the user space address to retrieve the long from

Description

Returns the long value from a given user space address. Returns zero when user space and warns (but does not abort) about the failure. Note that the size of the long depends on the architecture of the current user space task (for those architectures that support both 64/32 bit compat tasks).

function::user_short

function::user_short — Retrieves a short value stored in user space

Synopsis

```
user_short:long(addr:long)
```

Arguments

addr the user space address to retrieve the short from

Description

Returns the short value from a given user space address. Returns zero when user space data is not accessible.

function::user_short_warn

function::user_short_warn — Retrieves a short value stored in user space

Synopsis

```
user_short_warn:long(addr:long)
```

Arguments

addr the user space address to retrieve the short from

Description

Returns the short value from a given user space address. Returns zero when user space and warns (but does not abort) about the failure.

function::user_string

function::user_string — Retrieves string from user space

Synopsis

```
user_string:string(addr:long)
```

Arguments

addr the user space address to retrieve the string from

Description

Returns the null terminated C string from a given user space memory address. Reports an error on the rare cases when userspace data is not accessible.

function::user_string2

function::user_string2 — Retrieves string from user space with alternative error string

Synopsis

```
user_string2:string(addr:long,err_msg:string)
```

Arguments

addr the user space address to retrieve the string from

err_msg the error message to return when data isn't available

Description

Returns the null terminated C string from a given user space memory address. Reports the given error message on the rare cases when userspace data is not accessible.

function::user_string2_n_warn

function::user_string2_n_warn — Retrieves string from user space with alternative warning string

Synopsis

```
user_string2_n_warn:string(addr:long,n:long,warn_msg:string)
```

Arguments

<i>addr</i>	the user space address to retrieve the string from
<i>n</i>	the maximum length of the string (if not null terminated)
<i>warn_msg</i>	the warning message to return when data isn't available

Description

Returns up to n characters of a C string from a given user space memory address. Reports the given warning message on the rare cases when userspace data is not accessible and warns (but does not abort) about the failure.

function::user_string2_utf16

function::user_string2_utf16 — Retrieves UTF-16 string from user memory with alternative error string

Synopsis

```
user_string2_utf16:string(addr:long,err_msg:string)
```

Arguments

addr The user address to retrieve the string from

err_msg The error message to return when data isn't available

Description

This function returns a null terminated UTF-8 string converted from the UTF-16 string at a given user memory address. Reports the given error message on string copy fault or conversion error.

function::user_string2_utf32

function::user_string2_utf32 — Retrieves UTF-32 string from user memory with alternative error string

Synopsis

```
user_string2_utf32:string(addr:long,err_msg:string)
```

Arguments

addr The user address to retrieve the string from

err_msg The error message to return when data isn't available

Description

This function returns a null terminated UTF-8 string converted from the UTF-32 string at a given user memory address. Reports the given error message on string copy fault or conversion error.

function::user_string2_warn

function::user_string2_warn — Retrieves string from user space with alternative warning string

Synopsis

```
user_string2_warn:string(addr:long,warn_msg:string)
```

Arguments

addr the user space address to retrieve the string from

warn_msg the warning message to return when data isn't available

Description

Returns the null terminated C string from a given user space memory address. Reports the given warning message on the rare cases when userspace data is not accessible and warns (but does not abort) about the failure.

function::user_string_n

function::user_string_n — Retrieves string of given length from user space

Synopsis

```
user_string_n:string(addr:long,n:long)
```

Arguments

addr the user space address to retrieve the string from

n the maximum length of the string (if not null terminated)

Description

Returns the C string of a maximum given length from a given user space address. Reports an error on the rare cases when userspace data is not accessible at the given address.

function::user_string_n2

function::user_string_n2 — Retrieves string of given length from user space

Synopsis

```
user_string_n2:string(addr:long,n:long,err_msg:string)
```

Arguments

<i>addr</i>	the user space address to retrieve the string from
<i>n</i>	the maximum length of the string (if not null terminated)
<i>err_msg</i>	the error message to return when data isn't available

Description

Returns the C string of a maximum given length from a given user space address. Returns the given error message string on the rare cases when userspace data is not accessible at the given address.

function::user_string_n_quoted

function::user_string_n_quoted — Retrieves and quotes string from user space

Synopsis

```
user_string_n_quoted:string(addr:long,n:long)
```

Arguments

addr the user space address to retrieve the string from

n the maximum length of the string (if not null terminated)

Description

Returns up to n characters of a C string from the given user space memory address where any ASCII characters that are not printable are replaced by the corresponding escape sequence in the returned string. Note that the string will be surrounded by double quotes. On the rare cases when userspace data is not accessible at the given address, the address itself is returned as a string, without double quotes.

function::user_string_n_warn

function::user_string_n_warn — Retrieves string from user space

Synopsis

```
user_string_n_warn:string(addr:long,n:long)
```

Arguments

addr the user space address to retrieve the string from

n the maximum length of the string (if not null terminated)

Description

Returns up to *n* characters of a C string from a given user space memory address. Reports “<unknown>” on the rare cases when userspace data is not accessible and warns (but does not abort) about the failure.

function::user_string_quoted

function::user_string_quoted — Retrieves and quotes string from user space

Synopsis

```
user_string_quoted:string(addr:long)
```

Arguments

addr the user space address to retrieve the string from

Description

Returns the null terminated C string from a given user space memory address where any ASCII characters that are not printable are replaced by the corresponding escape sequence in the returned string. Note that the string will be surrounded by double quotes. On the rare cases when userspace data is not accessible at the given address, the address itself is returned as a string, without double quotes.

function::user_string_utf16

function::user_string_utf16 — Retrieves UTF-16 string from user memory

Synopsis

```
user_string_utf16:string(addr:long)
```

Arguments

addr The user address to retrieve the string from

Description

This function returns a null terminated UTF-8 string converted from the UTF-16 string at a given user memory address. Reports an error on string copy fault or conversion error.

function::user_string_utf32

function::user_string_utf32 — Retrieves UTF-32 string from user memory

Synopsis

```
user_string_utf32:string(addr:long)
```

Arguments

addr The user address to retrieve the string from

Description

This function returns a null terminated UTF-8 string converted from the UTF-32 string at a given user memory address. Reports an error on string copy fault or conversion error.

function::user_string_warn

function::user_string_warn — Retrieves string from user space

Synopsis

```
user_string_warn:string(addr:long)
```

Arguments

addr the user space address to retrieve the string from

Description

Returns the null terminated C string from a given user space memory address. Reports "" on the rare cases when userspace data is not accessible and warns (but does not abort) about the failure.

function::user_uint16

function::user_uint16 — Retrieves an unsigned 16-bit integer value stored in user space

Synopsis

```
user_uint16:long(addr:long)
```

Arguments

addr the user space address to retrieve the unsigned 16-bit integer from

Description

Returns the unsigned 16-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_uint32

function::user_uint32 — Retrieves an unsigned 32-bit integer value stored in user space

Synopsis

```
user_uint32:long(addr:long)
```

Arguments

addr the user space address to retrieve the unsigned 32-bit integer from

Description

Returns the unsigned 32-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_uint64

function::user_uint64 — Retrieves an unsigned 64-bit integer value stored in user space

Synopsis

```
user_uint64:long(addr:long)
```

Arguments

addr the user space address to retrieve the unsigned 64-bit integer from

Description

Returns the unsigned 64-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_uint8

function::user_uint8 — Retrieves an unsigned 8-bit integer value stored in user space

Synopsis

```
user_uint8:long(addr:long)
```

Arguments

addr the user space address to retrieve the unsigned 8-bit integer from

Description

Returns the unsigned 8-bit integer value from a given user space address. Returns zero when user space data is not accessible.

function::user_ushort

function::user_ushort — Retrieves an unsigned short value stored in user space

Synopsis

```
user_ushort:long(addr:long)
```

Arguments

addr the user space address to retrieve the unsigned short from

Description

Returns the unsigned short value from a given user space address. Returns zero when user space data is not accessible.

function::user_ushort_warn

function::user_ushort_warn — Retrieves an unsigned short value stored in user space

Synopsis

```
user_ushort_warn:long(addr:long)
```

Arguments

addr the user space address to retrieve the unsigned short from

Description

Returns the unsigned short value from a given user space address. Returns zero when user space and warns (but does not abort) about the failure.

Chapter 25. String and data writing functions Tapset

The SystemTap guru mode can be used to test error handling in kernel code by simulating faults. The functions in the this tapset provide standard methods of writing to primitive types in the kernel's memory. All the functions in this tapset require the use of guru mode (**-g**).

function::set_kernel_char

function::set_kernel_char — Writes a char value to kernel memory

Synopsis

```
set_kernel_char(addr:long,val:long)
```

Arguments

addr The kernel address to write the char to

val The char which is to be written

Description

Writes the char value to a given kernel memory address. Reports an error when writing to the given address fails. Requires the use of guru mode (-g).

function::set_kernel_int

function::set_kernel_int — Writes an int value to kernel memory

Synopsis

```
set_kernel_int(addr:long, val:long)
```

Arguments

addr The kernel address to write the int to

val The int which is to be written

Description

Writes the int value to a given kernel memory address. Reports an error when writing to the given address fails. Requires the use of guru mode (-g).

function::set_kernel_long

function::set_kernel_long — Writes a long value to kernel memory

Synopsis

```
set_kernel_long(addr:long,val:long)
```

Arguments

addr The kernel address to write the long to

val The long which is to be written

Description

Writes the long value to a given kernel memory address. Reports an error when writing to the given address fails. Requires the use of guru mode (-g).

function::set_kernel_pointer

function::set_kernel_pointer — Writes a pointer value to kernel memory.

Synopsis

```
set_kernel_pointer(addr:long,val:long)
```

Arguments

addr The kernel address to write the pointer to

val The pointer which is to be written

Description

Writes the pointer value to a given kernel memory address. Reports an error when writing to the given address fails. Requires the use of guru mode (-g).

function::set_kernel_short

function::set_kernel_short — Writes a short value to kernel memory

Synopsis

```
set_kernel_short(addr:long,val:long)
```

Arguments

addr The kernel address to write the short to

val The short which is to be written

Description

Writes the short value to a given kernel memory address. Reports an error when writing to the given address fails. Requires the use of guru mode (-g).

function::set_kernel_string

function::set_kernel_string — Writes a string to kernel memory

Synopsis

```
set_kernel_string(addr:long, val:string)
```

Arguments

addr The kernel address to write the string to

val The string which is to be written

Description

Writes the given string to a given kernel memory address. Reports an error on string copy fault. Requires the use of guru mode (-g).

function::set_kernel_string_n

function::set_kernel_string_n — Writes a string of given length to kernel memory

Synopsis

```
set_kernel_string_n(addr:long,n:long,val:string)
```

Arguments

addr The kernel address to write the string to

n The maximum length of the string

val The string which is to be written

Description

Writes the given string up to a maximum given length to a given kernel memory address. Reports an error on string copy fault. Requires the use of guru mode (-g).

Chapter 26. Guru tapsets

Functions to deliberately interfere with the system's behavior, in order to inject faults or improve observability. All the functions in this tapset require the use of guru mode (`-g`).

function::mdelay

function::mdelay — millisecond delay

Synopsis

```
mdelay(ms:long)
```

Arguments

ms Number of milliseconds to delay.

Description

This function inserts a multi-millisecond busy-delay into a probe handler. It requires guru mode.

function::panic

function::panic — trigger a panic

Synopsis

```
panic(msg:string)
```

Arguments

msg message to pass to kernel's `panic` function

Description

This function triggers an immediate panic of the running kernel with a user-specified panic message. It requires guru mode.

function::raise

function::raise — raise a signal in the current thread

Synopsis

```
raise(signo:long)
```

Arguments

signo signal number

Description

This function calls the kernel send_sig routine on the current thread, with the given raw unchecked signal number. It may raise an error if send_sig failed. It requires guru mode.

function::udelay

function::udelay — microsecond delay

Synopsis

```
udelay(us:long)
```

Arguments

us Number of microseconds to delay.

Description

This function inserts a multi-microsecond busy-delay into a probe handler. It requires guru mode.

Chapter 27. A collection of standard string functions

Functions to get the length, a substring, getting at individual characters, string searching, escaping, tokenizing, and converting strings to longs.

function::isdigit

function::isdigit — Checks for a digit

Synopsis

```
isdigit:long(str:string)
```

Arguments

str string to check

Description

Checks for a digit (0 through 9) as the first character of a string. Returns non-zero if true, and a zero if false.

function::isinstr

function::isinstr — Returns whether a string is a substring of another string

Synopsis

```
isinstr:long(s1:string,s2:string)
```

Arguments

s1 string to search in

s2 substring to find

Description

This function returns 1 if string *s1* contains *s2*, otherwise zero.

function::str_replace

function::str_replace — str_replace Replaces all instances of a substring with another

Synopsis

```
str_replace:string(prnt_str:string,srch_str:string,rplc_str:string)
```

Arguments

prnt_str the string to search and replace in

srch_str the substring which is used to search in *prnt_str* string

rplc_str the substring which is used to replace *srch_str*

Description

This function returns the given string with substrings replaced.

function::stringat

function::stringat — Returns the char at a given position in the string

Synopsis

```
stringat:long(str:string, pos:long)
```

Arguments

str the string to fetch the character from

pos the position to get the character from (first character is 0)

Description

This function returns the character at a given position in the string or zero if the string doesn't have as many characters. Reports an error if pos is out of bounds.

function::strlen

function::strlen — Returns the length of a string

Synopsis

```
strlen:long(s:string)
```

Arguments

s the string

Description

This function returns the length of the string, which can be zero up to MAXSTRINGLEN.

function::strtol

function::strtol — strtol - Convert a string to a long

Synopsis

```
strtol:long(str:string,base:long)
```

Arguments

str string to convert

base the base to use

Description

This function converts the string representation of a number to an integer. The *base* parameter indicates the number base to assume for the string (eg. 16 for hex, 8 for octal, 2 for binary).

function::substr

function::substr — Returns a substring

Synopsis

```
substr:string(str:string,start:long,length:long)
```

Arguments

str the string to take a substring from

start starting position of the extracted string (first character is 0)

length length of string to return

Description

Returns the substring of the given string at the given start position with the given length (or smaller if the length of the original string is less than start + length, or length is bigger than MAXSTRINGLEN).

function::text_str

function::text_str — Escape any non-printable chars in a string

Synopsis

```
text_str:string(input:string)
```

Arguments

input the string to escape

Description

This function accepts a string argument, and any ASCII characters that are not printable are replaced by the corresponding escape sequence in the returned string.

function::text_strn

function::text_strn — Escape any non-printable chars in a string

Synopsis

```
text_strn:string(input:string,len:long,quoted:long)
```

Arguments

input the string to escape

len maximum length of string to return (0 implies MAXSTRINGLEN)

quoted put double quotes around the string. If input string is truncated it will have “...” after the second quote

Description

This function accepts a string of designated length, and any ASCII characters that are not printable are replaced by the corresponding escape sequence in the returned string.

function::tokenize

function::tokenize — Return the next non-empty token in a string

Synopsis

```
tokenize:string(input:string,delim:string)
```

Arguments

input string to tokenize. If empty, returns the next non-empty token in the string passed in the previous call to `tokenize`.

delim set of characters that delimit the tokens

Description

This function returns the next non-empty token in the given input string, where the tokens are delimited by characters in the `delim` string. If the input string is non-empty, it returns the first token. If the input string is empty, it returns the next token in the string passed in the previous call to `tokenize`. If no delimiter is found, the entire remaining input string is returned. It returns empty when no more tokens are available.

Chapter 28. Utility functions for using ansi control chars in logs

Utility functions for logging using ansi control characters. This lets you manipulate the cursor position and character color output and attributes of log messages.

function::ansi_clear_screen

function::ansi_clear_screen — Move cursor to top left and clear screen.

Synopsis

```
ansi_clear_screen()
```

Arguments

None

Description

Sends ansi code for moving cursor to top left and then the ansi code for clearing the screen from the cursor position to the end.

function::ansi_cursor_hide

function::ansi_cursor_hide — Hides the cursor.

Synopsis

```
ansi_cursor_hide()
```

Arguments

None

Description

Sends ansi code for hiding the cursor.

function::ansi_cursor_move

function::ansi_cursor_move — Move cursor to new coordinates.

Synopsis

```
ansi_cursor_move(x:long,y:long)
```

Arguments

x Row to move the cursor to.

y Column to move the cursor to.

Description

Sends ansi code for positioning the cursor at row *x* and column *y*. Coordinates start at one, (1,1) is the top-left corner.

function::ansi_cursor_restore

function::ansi_cursor_restore — Restores a previously saved cursor position.

Synopsis

```
ansi_cursor_restore()
```

Arguments

None

Description

Sends ansi code for restoring the current cursor position previously saved with `ansi_cursor_save`.

function::ansi_cursor_save

function::ansi_cursor_save — Saves the cursor position.

Synopsis

```
ansi_cursor_save()
```

Arguments

None

Description

Sends ansi code for saving the current cursor position.

function::ansi_cursor_show

function::ansi_cursor_show — Shows the cursor.

Synopsis

```
ansi_cursor_show()
```

Arguments

None

Description

Sends ansi code for showing the cursor.

function::ansi_new_line

function::ansi_new_line — Move cursor to new line.

Synopsis

```
ansi_new_line()
```

Arguments

None

Description

Sends ansi code new line.

function::ansi_reset_color

function::ansi_reset_color — Resets Select Graphic Rendition mode.

Synopsis

```
ansi_reset_color()
```

Arguments

None

Description

Sends ansi code to reset foreground, background and color attribute to default values.

function::ansi_set_color

function::ansi_set_color — Set the ansi Select Graphic Rendition mode.

Synopsis

```
ansi_set_color(fg:long)
```

Arguments

fg Foreground color to set.

Description

Sends ansi code for Select Graphic Rendition mode for the given foreground color. Black (30), Blue (34), Green (32), Cyan (36), Red (31), Purple (35), Brown (33), Light Gray (37).

function::ansi_set_color2

function::ansi_set_color2 — Set the ansi Select Graphic Rendition mode.

Synopsis

```
ansi_set_color2(fg:long,bg:long)
```

Arguments

fg Foreground color to set.

bg Background color to set.

Description

Sends ansi code for Select Graphic Rendition mode for the given foreground color, Black (30), Blue (34), Green (32), Cyan (36), Red (31), Purple (35), Brown (33), Light Gray (37) and the given background color, Black (40), Red (41), Green (42), Yellow (43), Blue (44), Magenta (45), Cyan (46), White (47).

function::ansi_set_color3

function::ansi_set_color3 — Set the ansi Select Graphic Rendition mode.

Synopsis

```
ansi_set_color3(fg:long,bg:long,attr:long)
```

Arguments

fg Foreground color to set.

bg Background color to set.

attr Color attribute to set.

Description

Sends ansi code for Select Graphic Rendition mode for the given foreground color, Black (30), Blue (34), Green (32), Cyan (36), Red (31), Purple (35), Brown (33), Light Gray (37), the given background color, Black (40), Red (41), Green (42), Yellow (43), Blue (44), Magenta (45), Cyan (46), White (47) and the color attribute All attributes off (0), Intensity Bold (1), Underline Single (4), Blink Slow (5), Blink Rapid (6), Image Negative (7).

function::indent

function::indent — returns an amount of space to indent

Synopsis

```
indent:string(delta:long)
```

Arguments

delta the amount of space added/removed for each call

Description

This function returns a string with appropriate indentation. Call it with a small positive or matching negative delta. Unlike the thread_indent function, the indent does not track individual indent values on a per thread basis.

function::thread_indent

function::thread_indent — returns an amount of space with the current task information

Synopsis

```
thread_indent:string(delta:long)
```

Arguments

delta the amount of space added/removed for each call

Description

This function returns a string with appropriate indentation for a thread. Call it with a small positive or matching negative delta. If this is the real outermost, initial level of indentation, then the function resets the relative timestamp base to zero. An example is shown at the end of this file.

Chapter 29. SystemTap Translator Tapset

This family of user-space probe points is used to probe the operation of the SystemTap translator (**stap**) and run command (**staprun**). The tapset includes probes to watch the various phases of SystemTap and SystemTap's management of instrumentation cache. It contains the following probe points:

probe::stap.cache_add_mod

probe::stap.cache_add_mod — Adding kernel instrumentation module to cache

Synopsis

`stap.cache_add_mod`

Values

dest_path the path the .ko file is going to (incl filename)

source_path the path the .ko file is coming from (incl filename)

Description

Fires just before the file is actually moved. Note: if moving fails, `cache_add_src` and `cache_add_nss` will not fire.

probe::stap.cache_add_nss

probe::stap.cache_add_nss — Add NSS (Network Security Services) information to cache

Synopsis

```
stap.cache_add_nss
```

Values

source_path the path the .sgn file is coming from (incl filename)

dest_path the path the .sgn file is coming from (incl filename)

Description

Fires just before the file is actually moved. Note: stap must compiled with NSS support; if moving the kernel module fails, this probe will not fire.

probe::stap.cache_add_src

probe::stap.cache_add_src — Adding C code translation to cache

Synopsis

```
stap.cache_add_src
```

Values

source_path the path the .c file is coming from (incl filename)

dest_path the path the .c file is going to (incl filename)

Description

Fires just before the file is actually moved. Note: if moving the kernel module fails, this probe will not fire.

probe::stap.cache_clean

probe::stap.cache_clean — Removing file from stap cache

Synopsis

```
stap.cache_clean
```

Values

path the path to the .ko/.c file being removed

Description

Fires just before the call to unlink the module/source file.

probe::stap.cache_get

probe::stap.cache_get — Found item in stap cache

Synopsis

`stap.cache_get`

Values

source_path the path of the .c source file

module_path the path of the .ko kernel module file

Description

Fires just before the return of `get_from_cache`, when the cache grab is successful.

probe::stap.pass0

probe::stap.pass0 — Starting stap pass0 (parsing command line arguments)

Synopsis

`stap.pass0`

Values

session the systemtap_session variable s

Description

pass0 fires after command line arguments have been parsed.

probe::stap.pass0.end

probe::stap.pass0.end — Finished stap pass0 (parsing command line arguments)

Synopsis

`stap.pass0.end`

Values

`session` the systemtap_session variable s

Description

pass0.end fires just before the `gettimeofday` call for pass1.

probe::stap.pass1.end

probe::stap.pass1.end — Finished stap pass1 (parsing scripts)

Synopsis

`stap.pass1.end`

Values

`session` the systemtap_session variable s

Description

`pass1.end` fires just before the jump to cleanup if `s.last_pass = 1`.

probe::stap.pass1a

probe::stap.pass1a — Starting stap pass1 (parsing user script)

Synopsis

`stap.pass1a`

Values

`session` the systemtap_session variable s

Description

pass1a fires just after the call to `gettimeofday`, before the user script is parsed.

probe::stap.pass1b

probe::stap.pass1b — Starting stap pass1 (parsing library scripts)

Synopsis

`stap.pass1b`

Values

`session` the systemtap_session variable s

Description

pass1b fires just before the library scripts are parsed.

probe::stap.pass2

probe::stap.pass2 — Starting stap pass2 (elaboration)

Synopsis

`stap.pass2`

Values

session the systemtap_session variable s

Description

pass2 fires just after the call to `gettimeofday`, just before the call to `semantic_pass`.

probe::stap.pass2.end

probe::stap.pass2.end — Finished stap pass2 (elaboration)

Synopsis

`stap.pass2.end`

Values

`session` the systemtap_session variable s

Description

pass2.end fires just before the jump to cleanup if s.last_pass = 2

probe::stap.pass3

probe::stap.pass3 — Starting stap pass3 (translation to C)

Synopsis

`stap.pass3`

Values

session the systemtap_session variable s

Description

pass3 fires just after the call to `gettimeofday`, just before the call to `translate_pass`.

probe::stap.pass3.end

probe::stap.pass3.end — Finished stap pass3 (translation to C)

Synopsis

`stap.pass3.end`

Values

`session` the systemtap_session variable s

Description

pass3.end fires just before the jump to cleanup if s.last_pass = 3

probe::stap.pass4

`probe::stap.pass4` — Starting stap pass4 (compile C code into kernel module)

Synopsis

`stap.pass4`

Values

`session` the systemtap_session variable s

Description

pass4 fires just after the call to `gettimeofday`, just before the call to `compile_pass`.

probe::stap.pass4.end

probe::stap.pass4.end — Finished stap pass4 (compile C code into kernel module)

Synopsis

`stap.pass4.end`

Values

`session` the systemtap_session variable s

Description

pass4.end fires just before the jump to cleanup if s.last_pass = 4

probe::stap.pass5

probe::stap.pass5 — Starting stap pass5 (running the instrumentation)

Synopsis

`stap.pass5`

Values

session the systemtap_session variable s

Description

pass5 fires just after the call to `gettimeofday`, just before the call to `run_pass`.

probe::stap.pass5.end

probe::stap.pass5.end — Finished stap pass5 (running the instrumentation)

Synopsis

`stap.pass5.end`

Values

session the systemtap_session variable s

Description

pass5.end fires just before the cleanup label

probe::stap.pass6

probe::stap.pass6 — Starting stap pass6 (cleanup)

Synopsis

`stap.pass6`

Values

session the systemtap_session variable s

Description

pass6 fires just after the cleanup label, essentially the same spot as pass5.end

probe::stap.pass6.end

probe::stap.pass6.end — Finished stap pass6 (cleanup)

Synopsis

`stap.pass6.end`

Values

`session` the systemtap_session variable s

Description

pass6.end fires just before main's return.

probe::stap.system

probe::stap.system — Starting a command from stap

Synopsis

`stap.system`

Values

command the command string to be run by posix_spawn (as sh -c <str>)

Description

Fires at the entry of the `stap_system` command.

probe::stap.system.return

probe::stap.system.return — Finished a command from stap

Synopsis

```
stap.system.return
```

Values

ret a return code associated with running waitpid on the spawned process; a non-zero value indicates error

Description

Fires just before the return of the `stap_system` function, after `waitpid`.

probe::stap.system.spawn

probe::stap.system.spawn — stap spawned new process

Synopsis

`stap.system.spawn`

Values

ret the return value from posix_spawn

pid the pid of the spawned process

Description

Fires just after the call to posix_spawn.

probe::stapio.receive_control_message

probe::stapio.receive_control_message — Received a control message

Synopsis

```
stapio.receive_control_message
```

Values

len the length (in bytes) of the data blob

type type of message being send; defined in runtime/transport/transport_msgs.h

data a ptr to a binary blob of data sent as the control message

Description

Fires just after a message was received and before it's processed.

probe::staprun.insert_module

`probe::staprun.insert_module` — Inserting SystemTap instrumentation module

Synopsis

```
staprun.insert_module
```

Values

path the full path to the .ko kernel module about to be inserted

Description

Fires just before the call to insert the module.

probe::staprun.remove_module

probe::staprun.remove_module — Removing SystemTap instrumentation module

Synopsis

```
staprun.remove_module
```

Values

name the stap module name to be removed (without the .ko extension)

Description

Fires just before the call to remove the module.

probe::staprune.send_control_message

probe::staprune.send_control_message — Sending a control message

Synopsis

```
staprune.send_control_message
```

Values

data a ptr to a binary blob of data sent as the control message

type type of message being send; defined in runtime/transport/transport_msgs.h

len the length (in bytes) of the data blob

Description

Fires at the beginning of the send_request function.

Chapter 30. Network File Storage Tapsets

This family of probe points is used to probe network file storage functions and operations.

function::nfserror

function::nfserror — Convert nfsd error number into string

Synopsis

```
nfserror:string(err:long)
```

Arguments

err errnum

Description

This function returns a string for the error number passed into the function.

probe::nfs.aop.readpage

probe::nfs.aop.readpage — NFS client synchronously reading a page

Synopsis

`nfs.aop.readpage`

Values

<i>i_size</i>	file length in bytes
<i>__page</i>	the address of page
<i>rsize</i>	read size (in bytes)
<i>file</i>	file argument
<i>sb_flag</i>	super block flags
<i>size</i>	number of pages to be read in this execution
<i>i_flag</i>	file flags
<i>page_index</i>	offset within mapping, can used a page identifier and position identifier in the page frame
<i>dev</i>	device identifier
<i>ino</i>	inode number

Description

Read the page over, only fires when a previous async read operation failed

probe::nfs.aop.readpages

probe::nfs.aop.readpages — NFS client reading multiple pages

Synopsis

`nfs.aop.readpages`

Values

<i>dev</i>	device identifier
<i>rpages</i>	read size (in pages)
<i>ino</i>	inode number
<i>size</i>	number of pages attempted to read in this execution
<i>nr_pages</i>	number of pages attempted to read in this execution
<i>file</i>	filp argument
<i>rsize</i>	read size (in bytes)

Description

Fires when in readahead way, read several pages once

probe::nfs.aop.release_page

probe::nfs.aop.release_page — NFS client releasing page

Synopsis

```
nfs.aop.release_page
```

Values

<i>ino</i>	inode number
<i>dev</i>	device identifier
<i>page_index</i>	offset within mapping, can used a page identifier and position identifier in the page frame
<i>size</i>	release pages
<i>page</i>	the address of page

Description

Fires when do a release operation on NFS.

probe::nfs.aop.set_page_dirty

probe::nfs.aop.set_page_dirty — NFS client marking page as dirty

Synopsis

`nfs.aop.set_page_dirty`

Values

page_flag page flags

__page the address of page

Description

This probe attaches to the generic `_set_page_dirty_nobuffers` function. Thus, this probe is going to fire on many other file systems in addition to the NFS client.

probe::nfs.aop.write_begin

probe::nfs.aop.write_begin — NFS client begin to write data

Synopsis

`nfs.aop.write_begin`

Values

<code>__page</code>	the address of page
<code>to</code>	end address of this write operation
<code>offset</code>	start address of this write operation
<code>size</code>	write bytes
<code>ino</code>	inode number
<code>dev</code>	device identifier
<code>page_index</code>	offset within mapping, can used a page identifier and position identifier in the page frame

Description

Occurs when write operation occurs on nfs. It prepare a page for writing, look for a request corresponding to the page. If there is one, and it belongs to another file, it flush it out before it tries to copy anything into the page. Also do the same if it finds a request from an existing dropped page

probe::nfs.aop.write_end

probe::nfs.aop.write_end — NFS client complete writing data

Synopsis

`nfs.aop.write_end`

Values

<i>to</i>	end address of this write operation
<i>i_size</i>	file length in bytes
<i>sb_flag</i>	super block flags
<i>__page</i>	the address of page
<i>ino</i>	inode number
<i>dev</i>	device identifier
<i>page_index</i>	offset within mapping, can used a page identifier and position identifier in the page frame
<i>i_flag</i>	file flags
<i>size</i>	write bytes
<i>offset</i>	start address of this write operation

Description

Fires when do a write operation on nfs, often after prepare_write

Update and possibly write a cached page of an NFS file.

probe::nfs.aop.writepage

probe::nfs.aop.writepage — NFS client writing a mapped page to the NFS server

Synopsis

`nfs.aop.writepage`

Values

<i>page_index</i>	offset within mapping, can used a page identifier and position identifier in the page frame
<i>dev</i>	device identifier
<i>ino</i>	inode number
<i>size</i>	number of pages to be written in this execution
<i>i_flag</i>	file flags
<i>i_state</i>	inode state flags
<i>sb_flag</i>	super block flags
<i>wsize</i>	write size
<i>__page</i>	the address of page
<i>for_reclaim</i>	a flag of writeback_control, indicates if it's invoked from the page allocator
<i>for_kupdate</i>	a flag of writeback_control, indicates if it's a kupdate writeback
<i>i_size</i>	file length in bytes

Description

The priority of wb is decided by the flags *for_reclaim* and *for_kupdate*.

probe::nfs.aop.writepages

probe::nfs.aop.writepages — NFS client writing several dirty pages to the NFS server

Synopsis

`nfs.aop.writepages`

Values

for_reclaim a flag of writeback_control, indicates if it's invoked from the page allocator

wpages write size (in pages)

wsize write size

for_kupdate a flag of writeback_control, indicates if it's a kupdate writeback

nr_to_write number of pages attempted to be written in this execution

dev device identifier

ino inode number

size number of pages attempted to be written in this execution

Description

The priority of wb is decided by the flags *for_reclaim* and *for_kupdate*.

probe::nfs.fop.aio_read

probe::nfs.fop.aio_read — NFS client aio_read file operation

Synopsis

`nfs.fop.aio_read`

Values

<i>cache_time</i>	when we started read-caching this inode
<i>count</i>	read bytes
<i>attrtimeo</i>	how long the cached information is assumed to be valid. We need to revalidate the cached attrs for this inode if jiffies - read_cache_jiffies > attrtimeo.
<i>ino</i>	inode number
<i>cache_valid</i>	cache related bit mask flag
<i>pos</i>	current position of file
<i>dev</i>	device identifier
<i>file_name</i>	file name
<i>buf</i>	the address of buf in user space
<i>parent_name</i>	parent dir name

probe::nfs.fop.aio_write

probe::nfs.fop.aio_write — NFS client aio_write file operation

Synopsis

`nfs.fop.aio_write`

Values

parent_name parent dir name

buf the address of buf in user space

file_name file name

pos offset of the file

dev device identifier

ino inode number

count read bytes

probe::nfs.fop.check_flags

probe::nfs.fop.check_flags — NFS client checking flag operation

Synopsis

`nfs.fop.check_flags`

Values

flag file flag

probe::nfs.fop.flush

probe::nfs.fop.flush — NFS client flush file operation

Synopsis

`nfs.fop.flush`

Values

ndirty number of dirty page

dev device identifier

ino inode number

mode file mode

probe::nfs.fop.fsync

probe::nfs.fop.fsync — NFS client fsync operation

Synopsis

`nfs.fop.fsync`

Values

ndirty number of dirty pages

dev device identifier

ino inode number

probe::nfs.fop.llseek

probe::nfs.fop.llseek — NFS client llseek operation

Synopsis

`nfs.fop.llseek`

Values

whence_str symbolic string representation of the position to seek from

whence the position to seek from

dev device identifier

ino inode number

offset the offset of the file will be repositioned

probe::nfs.fop.lock

probe::nfs.fop.lock — NFS client file lock operation

Synopsis

`nfs.fop.lock`

Values

<i>i_mode</i>	file type and access rights
<i>fl_type</i>	lock type
<i>fl_flag</i>	lock flags
<i>fl_start</i>	starting offset of locked region
<i>ino</i>	inode number
<i>dev</i>	device identifier
<i>fl_end</i>	ending offset of locked region
<i>cmd</i>	cmd arguments

probe::nfs.fop.mmap

probe::nfs.fop.mmap — NFS client mmap operation

Synopsis

`nfs.fop.mmap`

Values

<i>cache_time</i>	when we started read-caching this inode
<i>vm_end</i>	the first byte after end address within vm_mm
<i>cache_valid</i>	cache related bit mask flag
<i>dev</i>	device identifier
<i>ino</i>	inode number
<i>attrtimeo</i>	how long the cached information is assumed to be valid. We need to revalidate the cached attrs for this inode if jiffies - read_cache_jiffies > attrtimeo.
<i>vm_flag</i>	vm flags
<i>parent_name</i>	parent dir name
<i>buf</i>	the address of buf in user space
<i>file_name</i>	file name
<i>vm_start</i>	start address within vm_mm

probe::nfs.fop.open

probe::nfs.fop.open — NFS client file open operation

Synopsis

`nfs.fop.open`

Values

i_size file length in bytes

file_name file name

flag file flag

dev device identifier

ino inode number

probe::nfs.fop.read

probe::nfs.fop.read — NFS client read operation

Synopsis

`nfs.fop.read`

Values

devname block device name

Description

SystemTap uses the vfs.do_sync_read probe to implement this probe and as a result will get operations other than the NFS client read operations.

probe::nfs.fop.release

probe::nfs.fop.release — NFS client release page operation

Synopsis

`nfs.fop.release`

Values

mode file mode

ino inode number

dev device identifier

probe::nfs.fop.sendfile

probe::nfs.fop.sendfile — NFS client send file operation

Synopsis

`nfs.fop.sendfile`

Values

<i>count</i>	read bytes
<i>attrtimeo</i>	how long the cached information is assumed to be valid. We need to revalidate the cached attrs for this inode if jiffies - read_cache_jiffies > attrtimeo.
<i>ino</i>	inode number
<i>cache_valid</i>	cache related bit mask flag
<i>dev</i>	device identifier
<i>cache_time</i>	when we started read-caching this inode
<i>ppos</i>	current position of file

probe::nfs.fop.write

probe::nfs.fop.write — NFS client write operation

Synopsis

```
nfs.fop.write
```

Values

devname block device name

Description

SystemTap uses the vfs.do_sync_write probe to implement this probe and as a result will get operations other than the NFS client write operations.

probe::nfs.proc.commit

probe::nfs.proc.commit — NFS client committing data on server

Synopsis

`nfs.proc.commit`

Values

version NFS version

bitmask1 V4 bitmask representing the set of attributes supported on this filesystem

size read bytes in this execution

offset the file offset

server_ip IP address of server

bitmask0 V4 bitmask representing the set of attributes supported on this filesystem

prot transfer protocol

Description

All the nfs.proc.commit kernel functions were removed in kernel commit 200baa in December 2006, so these probes do not exist on Linux 2.6.21 and newer kernels.

Fires when client writes the buffered data to disk. The buffered data is asynchronously written by client earlier. The commit function works in sync way. This probe point does not exist in NFSv2.

probe::nfs.proc.commit_done

probe::nfs.proc.commit_done — NFS client response to a commit RPC task

Synopsis

`nfs.proc.commit_done`

Values

<i>count</i>	number of bytes committed
<i>server_ip</i>	IP address of server
<i>version</i>	NFS version
<i>timestamp</i>	V4 timestamp, which is used for lease renewal
<i>status</i>	result of last operation
<i>valid</i>	fattr->valid, indicates which fields are valid
<i>prot</i>	transfer protocol

Description

Fires when a reply to a commit RPC task is received or some commit operation error occur (timeout or socket shutdown).

probe::nfs.proc.commit_setup

probe::nfs.proc.commit_setup — NFS client setting up a commit RPC task

Synopsis

```
nfs.proc.commit_setup
```

Values

<i>prot</i>	transfer protocol
<i>bitmask0</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>server_ip</i>	IP address of server
<i>count</i>	bytes in this commit
<i>version</i>	NFS version
<i>bitmask1</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>size</i>	bytes in this commit
<i>offset</i>	the file offset

Description

The commit_setup function is used to setup a commit RPC task. It is not doing the actual commit operation. It does not exist in NFSv2.

probe::nfs.proc.create

probe::nfs.proc.create — NFS client creating file on server

Synopsis

`nfs.proc.create`

Values

<i>filename</i>	file name
<i>prot</i>	transfer protocol
<i>filelen</i>	length of file name
<i>version</i>	NFS version (the function is used for all NFS version)
<i>flag</i>	indicates create mode (only for NFSv3 and NFSv4)
<i>server_ip</i>	IP address of server
<i>fh</i>	file handler of parent dir

probe::nfs.proc.handle_exception

`probe::nfs.proc.handle_exception` — NFS client handling an NFSv4 exception

Synopsis

`nfs.proc.handle_exception`

Values

`errorcode` indicates the type of error

Description

This is the error handling routine for processes for NFSv4.

probe::nfs.proc.lookup

probe::nfs.proc.lookup — NFS client opens/searches a file on server

Synopsis

`nfs.proc.lookup`

Values

<i>bitmask0</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>server_ip</i>	IP address of server
<i>name_len</i>	the length of file name
<i>bitmask1</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>prot</i>	transfer protocol
<i>version</i>	NFS version
<i>filename</i>	the name of file which client opens/searches on server

probe::nfs.proc.open

probe::nfs.proc.open — NFS client allocates file read/write context information

Synopsis

`nfs.proc.open`

Values

<i>prot</i>	transfer protocol
<i>filename</i>	file name
<i>version</i>	NFS version (the function is used for all NFS version)
<i>mode</i>	file mode
<i>server_ip</i>	IP address of server
<i>flag</i>	file flag

Description

Allocate file read/write context information

probe::nfs.proc.read

probe::nfs.proc.read — NFS client synchronously reads file from server

Synopsis

`nfs.proc.read`

Values

<i>offset</i>	the file offset
<i>version</i>	NFS version
<i>prot</i>	transfer protocol
<i>count</i>	read bytes in this execution
<i>server_ip</i>	IP address of server
<i>flags</i>	used to set task->tk_flags in rpc_init_task function

Description

All the nfs.proc.read kernel functions were removed in kernel commit 8e0969 in December 2006, so these probes do not exist on Linux 2.6.21 and newer kernels.

probe::nfs.proc.read_done

probe::nfs.proc.read_done — NFS client response to a read RPC task

Synopsis

`nfs.proc.read_done`

Values

<i>status</i>	result of last operation
<i>timestamp</i>	V4 timestamp, which is used for lease renewal
<i>prot</i>	transfer protocol
<i>server_ip</i>	IP address of server
<i>count</i>	number of bytes read
<i>version</i>	NFS version

Description

Fires when a reply to a read RPC task is received or some read error occurs (timeout or socket shutdown).

probe::nfs.proc.read_setup

probe::nfs.proc.read_setup — NFS client setting up a read RPC task

Synopsis

`nfs.proc.read_setup`

Values

<i>offset</i>	the file offset
<i>size</i>	read bytes in this execution
<i>version</i>	NFS version
<i>count</i>	read bytes in this execution
<i>server_ip</i>	IP address of server
<i>prot</i>	transfer protocol

Description

The read_setup function is used to setup a read RPC task. It is not doing the actual read operation.

probe::nfs.proc.release

probe::nfs.proc.release — NFS client releases file read/write context information

Synopsis

`nfs.proc.release`

Values

filename file name

prot transfer protocol

flag file flag

server_ip IP address of server

version NFS version (the function is used for all NFS version)

mode file mode

Description

Release file read/write context information

probe::nfs.proc.remove

probe::nfs.proc.remove — NFS client removes a file on server

Synopsis

`nfs.proc.remove`

Values

filelen length of file name

version NFS version (the function is used for all NFS version)

server_ip IP address of server

fh file handler of parent dir

filename file name

prot transfer protocol

probe::nfs.proc.rename

probe::nfs.proc.rename — NFS client renames a file on server

Synopsis

`nfs.proc.rename`

Values

<i>new_name</i>	new file name
<i>server_ip</i>	IP address of server
<i>old_filelen</i>	length of old file name
<i>new_fh</i>	file handler of new parent dir
<i>new_filelen</i>	length of new file name
<i>old_name</i>	old file name
<i>version</i>	NFS version (the function is used for all NFS version)
<i>prot</i>	transfer protocol
<i>old_fh</i>	file handler of old parent dir

probe::nfs.proc.write

probe::nfs.proc.write — NFS client synchronously writes file to server

Synopsis

`nfs.proc.write`

Values

<i>bitmask0</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>flags</i>	used to set task->tk_flags in rpc_init_task function
<i>server_ip</i>	IP address of server
<i>bitmask1</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>version</i>	NFS version
<i>size</i>	read bytes in this execution
<i>offset</i>	the file offset
<i>prot</i>	transfer protocol

Description

All the nfs.proc.write kernel functions were removed in kernel commit 200baa in December 2006, so these probes do not exist on Linux 2.6.21 and newer kernels.

probe::nfs.proc.write_done

probe::nfs.proc.write_done — NFS client response to a write RPC task

Synopsis

`nfs.proc.write_done`

Values

<i>prot</i>	transfer protocol
<i>valid</i>	fattr->valid, indicates which fields are valid
<i>timestamp</i>	V4 timestamp, which is used for lease renewal
<i>status</i>	result of last operation
<i>version</i>	NFS version
<i>server_ip</i>	IP address of server
<i>count</i>	number of bytes written

Description

Fires when a reply to a write RPC task is received or some write error occurs (timeout or socket shutdown).

probe::nfs.proc.write_setup

probe::nfs.proc.write_setup — NFS client setting up a write RPC task

Synopsis

`nfs.proc.write_setup`

Values

<i>prot</i>	transfer protocol
<i>count</i>	bytes written in this execution
<i>server_ip</i>	IP address of server
<i>bitmask0</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>how</i>	used to set args.stable. The stable value could be: NFS_UNSTABLE,NFS_DATA_SYNC,NFS_FILE_SYNC (in nfs.proc3.write_setup and nfs.proc4.write_setup)
<i>offset</i>	the file offset
<i>bitmask1</i>	V4 bitmask representing the set of attributes supported on this filesystem
<i>size</i>	bytes written in this execution
<i>version</i>	NFS version

Description

The write_setup function is used to setup a write RPC task. It is not doing the actual write operation.

probe::nfsd.close

probe::nfsd.close — NFS server closing a file for client

Synopsis

`nfsd.close`

Values

filename file name

probe::nfsd.commit

probe::nfsd.commit — NFS server committing all pending writes to stable storage

Synopsis

`nfsd.commit`

Values

<i>offset</i>	the offset of file
<i>fh</i>	file handle (the first part is the length of the file handle)
<i>size</i>	read bytes
<i>flag</i>	indicates whether this execution is a sync operation
<i>count</i>	read bytes
<i>client_ip</i>	the ip address of client

probe::nfsd.create

probe::nfsd.create — NFS server creating a file(regular,dir,device,fifo) for client

Synopsis

`nfsd.create`

Values

filelen the length of file name

client_ip the ip address of client

filename file name

type file type(regular,dir,device,fifo ...)

fh file handle (the first part is the length of the file handle)

iap_valid Attribute flags

iap_mode file access mode

Description

Sometimes nfsd will call nfsd_create_v3 instead of this this probe point.

probe::nfsd.createv3

probe::nfsd.createv3 — NFS server creating a regular file or set file attributes for client

Synopsis

`nfsd.createv3`

Values

<i>filename</i>	file name
<i>iap_valid</i>	Attribute flags
<i>createmode</i>	create mode .The possible values could be: NFS3_CREATE_EXCLUSIVE, NFS3_CREATE_UNCHECKED, or NFS3_CREATE_GUARDED
<i>fh</i>	file handle (the first part is the length of the file handle)
<i>truncp</i>	trunc arguments, indicates if the file shouldbe truncate
<i>iap_mode</i>	file access mode
<i>filelen</i>	the length of file name
<i>verifier</i>	file attributes (atime,mtime,mode). It's used to reset file attributes for CREATE_EXCLUSIVE
<i>client_ip</i>	the ip address of client

Description

This probepoints is only called by nfsd3_proc_create and nfsd4_open when op_claim_type is NFS4_OPEN_CLAIM_NULL.

probe::nfsd.dispatch

probe::nfsd.dispatch — NFS server receives an operation from client

Synopsis

`nfsd.dispatch`

Values

version nfs version

client_ip the ip address of client

proc procedure number

prog program number

xid transmission id

proto transfer protocol

probe::nfsd.lookup

probe::nfsd.lookup — NFS server opening or searching file for a file for client

Synopsis

`nfsd.lookup`

Values

filename file name

fh file handle of parent dir(the first part is the length of the file handle)

filelen the length of file name

client_ip the ip address of client

probe::nfsd.open

probe::nfsd.open — NFS server opening a file for client

Synopsis

`nfsd.open`

Values

<i>type</i>	type of file (regular file or dir)
<i>fh</i>	file handle (the first part is the length of the file handle)
<i>access</i>	indicates the type of open (read/write/commit/readdir...)
<i>client_ip</i>	the ip address of client

probe::nfsd.proc.commit

probe::nfsd.proc.commit — NFS server performing a commit operation for client

Synopsis

`nfsd.proc.commit`

Values

<i>gid</i>	requester's group id
<i>version</i>	nfs version
<i>count</i>	read bytes
<i>client_ip</i>	the ip address of client
<i>uid</i>	requester's user id
<i>fh</i>	file handle (the first part is the length of the file handle)
<i>offset</i>	the offset of file
<i>proto</i>	transfer protocol
<i>size</i>	read bytes

probe::nfsd.proc.create

probe::nfsd.proc.create — NFS server creating a file for client

Synopsis

`nfsd.proc.create`

Values

<i>fh</i>	file handle (the first part is the length of the file handle)
<i>uid</i>	requester's user id
<i>filename</i>	file name
<i>proto</i>	transfer protocol
<i>gid</i>	requester's group id
<i>filelen</i>	length of file name
<i>version</i>	nfs version
<i>client_ip</i>	the ip address of client

probe::nfsd.proc.lookup

probe::nfsd.proc.lookup — NFS server opening or searching for a file for client

Synopsis

`nfsd.proc.lookup`

Values

<i>filename</i>	file name
<i>uid</i>	requester's user id
<i>fh</i>	file handle of parent dir (the first part is the length of the file handle)
<i>proto</i>	transfer protocol
<i>version</i>	nfs version
<i>gid</i>	requester's group id
<i>filelen</i>	the length of file name
<i>client_ip</i>	the ip address of client

probe::nfsd.proc.read

probe::nfsd.proc.read — NFS server reading file for client

Synopsis

`nfsd.proc.read`

Values

<i>gid</i>	requester's group id
<i>count</i>	read bytes
<i>vlen</i>	read blocks
<i>version</i>	nfs version
<i>client_ip</i>	the ip address of client
<i>fh</i>	file handle (the first part is the length of the file handle)
<i>uid</i>	requester's user id
<i>offset</i>	the offset of file
<i>proto</i>	transfer protocol
<i>vec</i>	struct kvec, includes buf address in kernel address and length of each buffer
<i>size</i>	read bytes

probe::nfsd.proc.remove

probe::nfsd.proc.remove — NFS server removing a file for client

Synopsis

`nfsd.proc.remove`

Values

<i>gid</i>	requester's group id
<i>filelen</i>	length of file name
<i>version</i>	nfs version
<i>client_ip</i>	the ip address of client
<i>fh</i>	file handle (the first part is the length of the file handle)
<i>uid</i>	requester's user id
<i>filename</i>	file name
<i>proto</i>	transfer protocol

probe::nfsd.proc.rename

probe::nfsd.proc.rename — NFS Server renaming a file for client

Synopsis

`nfsd.proc.rename`

Values

<i>uid</i>	requester's user id
<i>fh</i>	file handler of old path
<i>filename</i>	old file name
<i>gid</i>	requester's group id
<i>flen</i>	length of old file name
<i>tfh</i>	file handler of new path
<i>tlen</i>	length of new file name
<i>tname</i>	new file name
<i>client_ip</i>	the ip address of client

probe::nfsd.proc.write

probe::nfsd.proc.write — NFS server writing data to file for client

Synopsis

`nfsd.proc.write`

Values

<i>client_ip</i>	the ip address of client
<i>stable</i>	argp->stable
<i>vlen</i>	read blocks
<i>count</i>	read bytes
<i>version</i>	nfs version
<i>gid</i>	requester's group id
<i>size</i>	read bytes
<i>vec</i>	struct kvec, includes buf address in kernel address and length of each buffer
<i>proto</i>	transfer protocol
<i>offset</i>	the offset of file
<i>uid</i>	requester's user id
<i>fh</i>	file handle (the first part is the length of the file handle)

probe::nfsd.read

probe::nfsd.read — NFS server reading data from a file for client

Synopsis

`nfsd.read`

Values

<i>count</i>	read bytes
<i>vlen</i>	read blocks
<i>client_ip</i>	the ip address of client
<i>offset</i>	the offset of file
<i>file</i>	argument file, indicates if the file has been opened.
<i>fh</i>	file handle (the first part is the length of the file handle)
<i>vec</i>	struct kvec, includes buf address in kernel address and length of each buffer
<i>size</i>	read bytes

probe::nfsd.rename

probe::nfsd.rename — NFS server renaming a file for client

Synopsis

`nfsd.rename`

Values

<i>fh</i>	file handler of old path
<i>filename</i>	old file name
<i>tlen</i>	length of new file name
<i>tname</i>	new file name
<i>client_ip</i>	the ip address of client
<i>tfh</i>	file handler of new path
<i>flen</i>	length of old file name

probe::nfsd.unlink

probe::nfsd.unlink — NFS server removing a file or a directory for client

Synopsis

`nfsd.unlink`

Values

fh file handle (the first part is the length of the file handle)

type file type (file or dir)

filename file name

filelen the length of file name

client_ip the ip address of client

probe::nfsd.write

probe::nfsd.write — NFS server writing data to a file for client

Synopsis

`nfsd.write`

Values

<i>client_ip</i>	the ip address of client
<i>count</i>	read bytes
<i>vlen</i>	read blocks
<i>size</i>	read bytes
<i>vec</i>	struct kvec, includes buf address in kernel address and length of each buffer
<i>file</i>	argument file, indicates if the file has been opened.
<i>offset</i>	the offset of file
<i>fh</i>	file handle (the first part is the length of the file handle)

Chapter 31. Speculation

This family of functions provides the ability to speculative record information and then at a later point in the SystemTap script either commit the information or discard it.

function::commit

function::commit — Write out all output related to a speculation buffer

Synopsis

```
commit(id:long)
```

Arguments

id of the buffer to store the information in

Description

Output all the output for *id* in the order that it was entered into the speculative buffer by `speculative`.

function::discard

function::discard — Discard all output related to a speculation buffer

Synopsis

```
discard(id:long)
```

Arguments

id of the buffer to store the information in

function::speculate

function::speculate — Store a string for possible output later

Synopsis

```
speculate(id:long,output:string)
```

Arguments

id buffer id to store the information in

output string to write out when commit occurs

Description

Add a string to the speculative buffer for *id*.

function::speculation

function::speculation — Allocate a new id for speculative output

Synopsis

```
speculation:long()
```

Arguments

None

Description

The `speculation` function is called when a new speculation buffer is needed. It returns an id for the speculative output. There can be multiple threads being speculated on concurrently. This id is used by other speculation functions to keep the threads separate.